
RRtoolbox Documentation

Release 1

davtoh

July 27, 2016

1	RRtoolbox package	3
1.1	Subpackages	3
1.1.1	RRtoolbox.lib package	3
	Subpackages	3
	Submodules	26
	RRtoolbox.lib.cache module	26
	RRtoolbox.lib.config module	31
	RRtoolbox.lib.descriptors module	32
	RRtoolbox.lib.directory module	35
	RRtoolbox.lib.image module	40
	RRtoolbox.lib.inspector module	52
	RRtoolbox.lib.plotter module	54
	RRtoolbox.lib.root module	62
	RRtoolbox.lib.serverServices module	67
	RRtoolbox.lib.session module	69
	Module contents	70
1.1.2	RRtoolbox.tools package	70
	Submodules	70
	RRtoolbox.tools.lens module	70
	RRtoolbox.tools.restoration module	71
	RRtoolbox.tools.segmentation module	73
	RRtoolbox.tools.selectors module	74
	RRtoolbox.tools.sticher module	75
	Module contents	75
1.2	Submodules	75
1.3	RRtoolbox.core module	75
1.4	RRtoolbox.run module	76
1.5	RRtoolbox.shell module	76
1.6	Module contents	76
2	Indices and tables	77
	Python Module Index	79
	Index	81

Contents:

RRtoolbox package

1.1 Subpackages

1.1.1 RRtoolbox.lib package

Subpackages

RRtoolbox.lib.arrayops package

Submodules

RRtoolbox.lib.arrayops.basic module This module contains simple array operation methods

`RRtoolbox.lib.arrayops.basic.angle (v1, v2, deg=False)`
 Angle between two N dimensional vectors.

Parameters

- **v1** – vector 1.
- **v2** – vector 2.
- **deg** – if True angle is in Degrees, else radians.

Returns angle in radians.

Example:

```
>>> angle_between((1, 0, 0), (0, 1, 0))
1.5707963267948966
>>> angle_between((1, 0, 0), (1, 0, 0))
0.0
>>> angle_between((1, 0, 0), (-1, 0, 0))
3.141592653589793
```

Note: obtained from <http://stackoverflow.com/a/13849249/5288758> and tested in <http://onlinemschool.com/math/assistance/vector/angle/>

`RRtoolbox.lib.arrayops.basic.angle2D (v1, v2, deg=False, absolute=None)`
 Angle between two 2 dimensional vectors.

Parameters

- **v1** – vector 1.
- **v2** – vector 2.
- **deg** – if True angle is in Degrees, else radians.
- **absolute** – if None returns the angle (0 to 180(pi)) between v1 and v2. if True returns the absolute angle (0 to 360(2pi)) from v1 as axis to v2. if False returns the angle (0 to 180 or 0 to -180) from v1 as axis to v2, where v2 angle relative to v1 is positive or negative if counter-clock or clock wise.

Returns angle in radians.

Note: implemented according to <http://math.stackexchange.com/a/747992> and tested in <http://onlinemschool.com/math/assistance/vector/angl/>

RRtoolbox.lib.arrayops.basic.**angleXY**(*coorX*, *coorY*, *angle*)

Rotate coordinate.

Parameters

- **coorX** – x coordinate.
- **coorY** – y coordinate.
- **angle** – radian angle.

Returns rotated x,y

RRtoolbox.lib.arrayops.basic.**anorm**(*a*)

norm in array.

Parameters **a** –

Returns

RRtoolbox.lib.arrayops.basic.**anorm2**(*a*)

Summation of squares (helper function for [anorm\(\)](#))

Parameters **a** –


Returns

RRtoolbox.lib.arrayops.basic.**axesIntercept**(*coorSM*, *maxS*, *maxM*)

Intercept static axis (S) and mobile axis (M) with a coordinate connecting both axes from minS to minM.

S1 S2

S0  maxS

coorSM 

M1 M2

M0  maxM

Parameters

- **coorSM** – coordinate of vector from S=0 to M=0.
- **maxS** – value representing end of estatic axis.
- **maxM** – value representing end of mobile axis.

Returns S1,S2,M1,M2.

`RRtoolbox.lib.arrayops.basic.boxPads (bx, points)`

Get box pads to fit all.

Parameters

- **bx** – box coordinates or previous boxPads [left_top, right_bottom]
- **points** – array of points

Returns [(left,top),(right,bottom)] where bx and points fit.

`RRtoolbox.lib.arrayops.basic.centerM (coor, maxM)`

Center vector coor in M axis.

Parameters

- **coor** – coordinate of vector from S=0 to M center
- **maxM** – value representing end of mobile axis

Returns M centered coordinate

`RRtoolbox.lib.arrayops.basic.centerS (coor, maxS)`

Center vector coor in S axis.

Parameters

- **coor** – coordinate of vector from S center to M=0
- **maxS** – value representing end of estatic axis

Returns S centered coordinate

`RRtoolbox.lib.arrayops.basic.centerSM (coorSM, maxS, maxM)`

Center vector coorSM in both S and M axes.

Parameters

- **coorSM** – coordinate of vector from S to M centers.
- **maxS** – value representing end of estatic axis.
- **maxM** – value representing end of mobile axis.

Returns SM centered coordinate.

`RRtoolbox.lib.arrayops.basic.contours2mask (contours, shape=None, astype=<type 'bool'>)`

Creates an array with filled polygons formed by contours.

Parameters

- **contours** – list of contour or points forming objects
- **shape** – (None) shape of array. If None it creates an array fitted to contours.
- **astype** – (“bool”) numpy type

Returns

`RRtoolbox.lib.arrayops.basic.contoursArea (contours)`

Accumulates areas from list of contours.

Parameters **contours** – list of contours or binary array.

Returns area.

RRtoolbox.lib.arrayops.basic.**convertXY**(*x*, *y*, *backshape*, *foreshape*, *flag*=0, *quartile*=0, *angle*=None)

Convert absolute XY 0,0 coordinates to new system WZ.

Parameters

- **x** – x coordinate.
- **y** – y coordinate.
- **backshape** – shape of background image.

:param foreshape: shape of foreground image. :param flag: flag for position (default=0).

- flag==0 : foreground to left up.
- flag==1 : foreground to left down.
- flag==2 : foreground to right up.
- flag==3 : foreground to right down.
- flag==4 : foreground at center of background.
- flag==5 : XY 0,0 is at center of background.
- flag==6 : XY 0,0 is at center of foreground.
- flag==7 : XY 0,0 is at right down of foreground.

Parameters

- **quartile** – place Mobile image at quartile 1,2,3,4. if left quartile=0 image won't be moved.
- **angle** – angle in radians (default=None). if None it does not apply.

Returns W,Z

RRtoolbox.lib.arrayops.basic.**convexityRatio**(*cnt*, *hull*=None)

Ratio to test if contours are irregular

Parameters **cnt** – contour

:param hull:(None) convex hull :return: ratio

RRtoolbox.lib.arrayops.basic.**entropyTest**(*arr*)

Entropy test of intensity arrays. (Helper function for `entropy()`)

Parameters **arr** – array MxN of dim 2.

Returns entropy.

RRtoolbox.lib.arrayops.basic.**find_near**(*m*, *thresh*=None, *side*=None)

helper function for findminima and findmaxima :param m: minima or maxima points :param thresh: guess or seed point :param side: left or right :return: value

RRtoolbox.lib.arrayops.basic.**findmaxima**(*hist*, *thresh*=None, *side*=None)

Get nearest peak value to a thresh point from a histogram.

Parameters

- **hist** – histogram
- **thresh** – initial seed
- **side** – find valley from left or right of thresh

Returns

RRtoolbox.lib.arrayops.basic.**findminima** (*hist, thresh=None, side=None*)

Get nearest valley value to a thresh point from a histogram.

Parameters

- **hist** – histogram
- **thresh** – initial seed
- **side** – find valley from left or right of thresh

Returns

RRtoolbox.lib.arrayops.basic.**getOtsuThresh** (*hist*)

From histogram calculate Otsu threshold value.

Parameters **hist** – histogram

Returns otsu threshold value

RRtoolbox.lib.arrayops.basic.**getTransformedCorners** (*shape, H*)

from shape gets transformed corners of array.

Parameters

- **shape** – H,W array shape
- **H** – transformation matrix

Returns upper_left, upper_right, lower_right, lower_left transformed corners.

RRtoolbox.lib.arrayops.basic.**getTransparency** (*array*)

Convert foreground to background.

Parameters **array** – image array.

Returns alfa (int or array)

RRtoolbox.lib.arrayops.basic.**get_x_space** (*funcs, step=10, xleft=-300, xright=300*)

get X axis space by brute force. This can be used to find the x points where the points in the y axis of any number of functions become stable.

Parameters

- **funcs** – list of functions
- **step** –
10. step to close guess to maximum
- **xleft** – maximum left limit
- **xright** – maximum right limit

Returns linspace

RRtoolbox.lib.arrayops.basic.**getdataVH** (*array, ypad=0, xpad=0, bgrcolor=None, alfa=None*)

Get data from array according to padding (Helper function for `padVH()`).

Parameters

- **array** – list of arrays to get data
- **ypad** – how much to pad in y axis
- **xpad** – how much to pad in x axis

Returns matrix_shapes, grid_div, row_grid, row_gridpad, globalgrid

RRtoolbox.lib.arrayops.basic.**histogram**(img)
Get image histogram.

Parameters **img** – gray or image with any bands

Returns histogram of every band

RRtoolbox.lib.arrayops.basic.**im2imFormat**(src, dst)
Tries to convert source image to destine image format.

Parameters

- **src** – source image.
- **dst** – destine image.

Returns reshaped source image.

RRtoolbox.lib.arrayops.basic.**im2shapeFormat**(im, shape)
Tries to convert image to intuited format from shape.

Parameters

- **im** – image.
- **shape** – shape to get format.
 shapes: * (None, None): converts to gray * (None, None, 2): converts to GR555 * (None, None, 3): converts to BGR * (None, None, 4): converts to BGRA

Returns reshaped image.

RRtoolbox.lib.arrayops.basic.**instability_bf**(funcs, step=10, maximum=300, guess=0, tolerance=0.01)
Find the instability of function approaching value by brute force,

Parameters

- **funcs** – list of functions
- **step** –
10. step to close guess to maximum
- **maximum** –
300. maximum value, if guess surpass this value then calculations are stopped.
- **guess** –
0. initial guess
- **tolerance** – (0.01) tolerance with last step to check instability.

Returns (state, updated guess). state is True if successful, else False.

RRtoolbox.lib.arrayops.basic.**invertM**(coordSM, maxM)
Invert M axis.

Parameters

- **coordSM** – coordinate of vector for M inverted axes.
- **maxS** – value representing end of estatic axis.
- **maxM** – value representing end of mobile axis.

Returns SM coordinate on S axis and inverted M axis.

RRtoolbox.lib.arrayops.basic.**invertSM**(*coordSM, maxS, maxM*)

Invert S and M axes.

Parameters

- **coordSM** – coordinate of vector for SM inverted axes.
- **maxS** – value representing end of estatic axis.
- **maxM** – value representing end of mobile axis.

Returns SM coordinate on inverted SM axes.

RRtoolbox.lib.arrayops.basic.**isnumpy**(*arr*)

Test whether an object is a numpy array. :param arr: :return: True if numpy array, else false.

RRtoolbox.lib.arrayops.basic.**makeVis**(*globalgrid, bgrcolor=None*)

Make visualization (Helper function for *padVH()*)

Parameters

- **globalgrid** – shape
- **bgrcolor** – color of visualization

Returns array of shape globalgrid

RRtoolbox.lib.arrayops.basic.**matrixIntercept**(*x, y, staticm, *mobilem*)

Intercepts planes x and y of a static matrix (staticm) with N mobile matrices (mobilem) translated from the origin to x,y coordinates.

Parameters

- **x** – x coordinate.
- **y** – y coordinate.
- **staticm** – static matrix.
- **mobilem** – mobile matrices.

Returns ROI of intercepted matrices [staticm,*mobilem].

RRtoolbox.lib.arrayops.basic.**multiple_superpose**(*base, fore, H, foremask=None*)

Superpose multiple foreground images to a single base image.

Parameters

- **base** – background, base or dipest level image (level -1)
- **fore** – foreground image list (in order of level i = 0, ... , N)
- **H** – transformation matrix of fore in level i to overlay in base
- **foremask** – foreground alfa mask in level i

Returns generator of each overlay

RRtoolbox.lib.arrayops.basic.**noisy**(*arr, mode*)

Add noise to arrays

Parameters

- **arr** – Input ndarray data (it will be converted to float).
- **mode** – noise method:
 - ‘gauss’ - Gaussian-distributed additive noise.

- 'poisson' - Poisson-distributed noise generated from the data.
- 's&p' - Replaces random pixels with 0 or 1.
- '**speckle**' - **Multiplicative noise using $out = arr + n*arr$, where n is uniform noise with specified mean & variance.**

:return noisy arr

RRtoolbox.lib.arrayops.basic.**normalize** (arr)

Normalize array to ensure range [0,1]

RRtoolbox.lib.arrayops.basic.**normalize2** (arr)

Normalize with factor of absolute maximum value.

RRtoolbox.lib.arrayops.basic.**normalizeCustom** (arr, by=<function amax>, axis=None)

Normalize array with custom operations.

Parameters

- **arr** – array (it does not correct negative values, use preferable NxM).
- **by** – np.max, np.sum or any function that gets an array to obtain factor.
- **axis** – if None it normalizes in all axes else in the selected axis.

Returns normalized to with factor.

RRtoolbox.lib.arrayops.basic.**overlay** (back, fore, alpha=None, alfainverted=False, under=False, flag=0)

Try to Overlay any dimension array.

Parameters

- **back** – BGRA background image.
- **fore** – BGRA foreground image.
- **alpha** – transparency channel.
- **alfainverted** – if True inverts alpha transparency.
- **under** – if True, place back as fore and fore as back.
- **flag** – (experimental)
 0. **Normally replace inverted transparency of alpha in back (N)**; superpose alpha in back (V).
 1. **Bloat and replace inverted transparency of alpha in back**; superpose bgr in back (V).
 2. Superpose inverted transparent COLOR of alpha in back.
 3. Superpose inverted transparent COLOR of alpha in back.
 4. **Superpose transparent of alpha in back**; superpose transparent COLOR of alpha in back.
 5. **Superpose transparent of alpha in back**; superpose transparent COLOR of alpha in back.

Returns overlayed array

See also:

`overlay2()`

RRtoolbox.lib.arrayops.basic.**overlay2** (back, fore)

Overlay foreground to x,y coordinates in background image.

Parameters

- **back** – background image (numpy array dim 3).
- **fore** – foreground image (numpy array dim 4). the fourth dimension is used for transparency.

Returns back (with overlay).

#Example:

```
import cv2
import numpy as np
import time
a= time.time()
back = cv2.imread("t1.jpg")
temp = back.shape
bgr = np.zeros((temp[0],temp[1],4), np.uint8)
points = [(86, 162), (1219, 1112), (2219, 2112), (1277,3000), (86, 162)]
col_in = (0, 0, 0,255)
thickness = 10
for i in range(len(points)-1):
    pt1 = (points[i][0], points[i][1])
    pt2 = (points[i+1][0], points[i+1][1])
    cv2.line(bgr, pt1, pt2, col_in, thickness)

overlay(back,bgr)

win = "overlay"
cv2.namedWindow(win,cv2.WINDOW_NORMAL)
cv2.imshow(win, back)
print time.time()-a
cv2.waitKey()
cv2.destroyAllWindows()
```

See also:

[`overlay\(\)`](#)

`RRtoolbox.lib.arrayops.basic.overlayXY(x, y, back, fore, alfa=None, alfainverted=False, under=False, flag=0)`

Overlay foreground image to x,y coordinates in background image. This function support images of different sizes with formats: BGR background and BGRA foreground of Opencv or numpy images.

Parameters

- **x** – x position in background.
- **y** – y position in background.
- **back** – background image (numpy array dim 3).
- **fore** – foreground image (numpy array dim 4). the fourth dimension is used for transparency.

Returns back (with overlay)

Example:

```
import cv2
back = cv2.imread("t1.jpg")
bgr = cv2.imread("mustache.png",-1)
x,y=convertXY(0,0,back.shape,bgr.shape,flag=1)
overlayXY(x,y,back,bgr)
```

```
win = "overlay"
cv2.namedWindow(win, cv2.WINDOW_NORMAL)
cv2.imshow(win, back)
cv2.waitKey()
cv2.destroyAllWindows()
```

RRtoolbox.lib.arrayops.basic.**overlaypng**(*back, fore, alpha=None, alfainverted=False, under=False, flag=0*)

Overlay only BGRA.

Parameters

- **back** – BGRA background image.
- **fore** – BGRA foreground image.
- **alpha** – transparency channel.
- **alfainverted** – if True inverts alpha transparency.
- **under** – if True, place back as fore and fore as back.
- **flag** – (experimental)
 0. **Normally replace inverted transparency of alpha in back (N)**; superpose alpha in back (V).
 1. **Bloat and replace inverted transparency of alpha in back**; superpose bgr in back (V).
 2. Superpose inverted transparent COLOR of alpha in back.
 3. Superpose inverted transparent COLOR of alpha in back.
 4. **Superpose transparent of alpha in back**; superpose transparent COLOR of alpha in back.
 5. **Superpose transparent of alpha in back**; superpose transparent COLOR of alpha in back.

Returns overlaid array

See also:

overlay(), *overlay2()*

RRtoolbox.lib.arrayops.basic.**padVH**(*imgs, ypad=0, xpad=0, bgrcolor=None, alfa=None*)

Pad Vertically and Horizontally image or group of images into an array.

Parameters

- **imgs** – image to pad or list of horizontal images (i.e. piled up horizontally as [V1,...,VN] where each can be a list of vertical piling VN = [H1,...,HM]. It can be successive like horizontals, verticals, horizontals, etc.
- **ypad** – padding in axis y
- **xpad** – padding in axis x
- **bgrcolor** – color of spaces
- **alfa** – transparency of imgs over background of bgrcolor color.

Returns visualization of padded and piled images in imgs.

RRtoolbox.lib.arrayops.basic.**pad_to_fit_H**(*shape1, shape2, H*)

get boxPads to fit transformed shape1 in shape2.

Parameters

- **shape1** – shape of array 1
- **shape2** – shape of array 2
- **H** – transformation matrix to use in shape1

Returns [(left,top),(right,bottom)]

RRtoolbox.lib.arrayops.basic.**points2mask** (*pts, shape=None, astype=<type 'bool'>*)
Creates an array with the filled polygon formed by points.

Parameters

- **pts** – points.
- **shape** – (None) shape of array. If None it creates an array fitted to points.
- **astype** – (“bool”) numpy type

Returns array.

Example:

```
pts = random_points([(-100, 100), (-100, 100)])
img = points2mask(pts)
plotim("filled",img).show()
```

RRtoolbox.lib.arrayops.basic.**points_generator** (*shape=(10, 10), noints=None, convex=False, erratic=False, complete=False*)

generate points.

Parameters

- **shape** – enclosed frame
- **noints** – number of points
- **convex** – if True make points convex, else points follow a circular pattern.

Returns

RRtoolbox.lib.arrayops.basic.**polygonArea** (*pts*)
Area of points calculating polygon Area.

Parameters **pts** – points.

Returns area value.

..note::

- If polygon is incomplete (last is not first point) it completes the array.
- If the polygon crosses over itself the algorithm will fail.
- Based on <http://www.mathopenref.com/coordpolygonarea.html>

RRtoolbox.lib.arrayops.basic.**polygonArea_calcule** (*pts*)
Area of points calculating polygon Area.

Parameters **pts** – points.

Returns area value.

..note::

- If polygon is incomplete (last is not first point) it completes the array.
- If the polygon crosses over itself the algorithm will fail.
- Based on <http://www.mathopenref.com/coordpolygonarea.html>

`RRtoolbox.lib.arrayops.basic.polygonArea_contour` (*pts*)

Area of points using contours.

Parameters *pts* – points.

Returns area value.

..note:: if polygon is incomplete (last is not first point) it completes the array.

`RRtoolbox.lib.arrayops.basic.polygonArea_fill` (*pts*)

Area of points using filled polygon and pixel count.

Parameters *pts* – points.

Returns area value.

..note:: if polygon is incomplete (last is not first point) it completes the array.

`RRtoolbox.lib.arrayops.basic.process_as_blocks` (*arr*, *func*, *block_shape*=(3, 3),
mask=None, *asWindows*=False)

process with function over an array using blocks (using re-striding).

Parameters

- **arr** – array to process
- **func** – function to feed blocks
- **block_shape** – (3,3) shape of blocks
- **mask** – (None) mask to process arr
- **asWindows** – (False) if True all blocks overlap each other to give a result for each position of arr, if False the results are given in blocks equivalent for each processed blocks of arr (faster).

Returns processed array.

`RRtoolbox.lib.arrayops.basic.quadrant` (*coorX*, *coorY*, *maxX*, *maxY*, *quadrant*=0)

Moves a point to a quadrant

Parameters

- **coorX** – point in x coordinate
- **coorY** – point in y coordinate
- **maxX** – max value in x axis
- **maxY** – max value in y axis
- **quadrant** – Cartesian quadrant, if 0 or False it leaves coorX and coorY unprocessed.

Returns

`RRtoolbox.lib.arrayops.basic.random_points` (*axes_range*=((-50, 50),), *nopoints*=4, *complete*=False)

Get random points.

Parameters

- **axes_range** – [x_points_range, y_points_range] where points_range is (min,max) range in axis.
- **nopoints** – number of points.
- **complete** – last point is the first point (adds an additional point i.e. nopoints+1).

Returns numpy array.

RRtoolbox.lib.arrayops.basic.**recursiveMap** (*function, sequence*)

Iterate recursively over a structure using a function.

Parameters

- **function** – function to apply
- **sequence** – iterator

Returns

RRtoolbox.lib.arrayops.basic.**relativeQuadrants** (*points*)

Get quadrants of relative vectors obtained from points. :param points: array of points. :return: quadrants.

RRtoolbox.lib.arrayops.basic.**relativeVectors** (*pts, all=True*)

Form vectors from points.

Parameters

- **pts** – array of points [p0, ... ,(x,y)].
- **all** – (True) if True adds last vector from last and first point.

Returns array of vectors [V0, ... , (V[n] = x[n+1]-x[n],y[n+1]-y[n])].

RRtoolbox.lib.arrayops.basic.**rescale** (*arr, max=1, min=0*)

Rescales array values to range [min,max].

Parameters

- **arr** – array.
- **max** – maximum value in range.
- **min** – minimum value in range.

Returns rescaled array.

RRtoolbox.lib.arrayops.basic.**separePointsByAxis** (*pts, ptaxis=(1, 0), origin=(0, 0)*)

Separate scattered points with respect to axis (splitting line).

Parameters

- **pts** – points to separate.
- **ptaxis** – point to form axis from origin
- **origin** – origin

Returns left, right points from axis.

RRtoolbox.lib.arrayops.basic.**splitPoints** (*pts, aslist=None*)

from points get x,y columns

Parameters

- **pts** – array of points
- **aslist** – True to return lists instead of arrays

Returns x, y columns

`RRtoolbox.lib.arrayops.basic.standardizePoints` (*pts, aslist=False*)

converts points to a standard form :param pts: list or array of points :param aslist: True to return list instead of array :return: standard points

`RRtoolbox.lib.arrayops.basic.superpose` (*back, fore, H, foreMask=None, grow=True*)

Superpose foreground image to background image.

Parameters

- **back** – background image
- **fore** – foreground image
- **H** – transformation matrix of fore to overlay in back
- **foreMask** – (None) foreground alpha mask, None or function. foreMask values are from 1 for solid to 0 for transparency. If a function is provided the new back,fore parameters are provided to produce the foreMask. If None is provided as foreMask then it is equivalent to a foreMask with all values to 1 where fore is True.
- **grow** – If True, im can be bigger than back and is calculated according to how fore is superposed in back; if False im is of the same shape as back.

Returns im, H_back, H_fore

`RRtoolbox.lib.arrayops.basic.transformPoint` (*p, H*)

Transform individual x,y point with Transformation Matrix.

Parameters

- **p** – x,y point
- **H** – transformation matrix

Returns transformed x,y point

`RRtoolbox.lib.arrayops.basic.transformPoints` (*p, H*)

Transform x,y points in array with Transformation Matrix.

Parameters

- **p** – array of points
- **H** – transformation matrix

Returns transformed array of x,y point

`RRtoolbox.lib.arrayops.basic.unit_vector` (*vector*)

Returns the unit vector of the vector.

`RRtoolbox.lib.arrayops.basic.vectorsAngles` (*pts, ptaxis=(1, 0), origin=(0, 0), dtype=None, deg=False, absolute=None*)

Angle of formed vectors in Cartesian plane with respect to formed axis vector.

i.e. angle between vector “Vn” (formed by point “Pn” and the “origin”)

and vector “Vaxis” formed by “ptaxis” and the “origin”.

where pts-origin = (P0-origin ... Pn-origin) = V0 ... Vn

Parameters

- **pts** – points to form vectors from origin
- **ptaxis** – point to form axis from origin

- **origin** – origin
- **dtype** – return array of type supported by numpy.
- **deg** – if True angle is in Degrees, else radians.
- **absolute** – if None returns angles (0 to 180(pi)) between pts-origin (V0 .. Vn) and Vaxis. if True returns any Vn absolute angle (0 to 360(2pi)) from Vaxis as axis to Vn. if False returns any Vn angle (0 to 180 or 0 to -180) from Vaxis as axis to Vn, where any Vn angle is positive or negative if counter-clock or clock wise from Vaxis.

Returns

RRtoolbox.lib.arrayops.basic.**vectorsQuadrants**(vecs)

Get quadrants of vectors.

Parameters **vecs** – array of vectors.

Returns quadrants.

RRtoolbox.lib.arrayops.basic.**vertexesAngles**(pts, dtype=None, deg=False)

Relative angle of vectors formed by vertexes (where vectors cross).

i.e. angle between vectors “v01” formed by points “p0-p1” and “v12” formed by points “p1-p2” where “p1” is seen as a vertex (where vectors cross).

Parameters

- **pts** – points seen as vertexes (vectors are recreated from point to point).
- **dtype** – return array of type supported by numpy.
- **deg** – if True angle is in Degrees, else radians.

Returns angles.

RRtoolbox.lib.arrayops.basic.**view_as_blocks**(arr_in, block_shape=(3, 3))

Provide a 2D block_shape view to 2D array. No error checking made. Therefore meaningful (as implemented) only for blocks strictly compatible with the shape of arr_in.

Parameters

- **arr_in** –
- **block_shape** –

Returns

RRtoolbox.lib.arrayops.basic.**view_as_windows**(arr_in, window_shape, step=1)

Provide a 2D block_shape rolling view to 2D array. No error checking made. Therefore meaningful (as implemented) only for blocks strictly compatible with the shape of arr_in.

Parameters

- **arr_in** –
- **window_shape** –
- **step** –

Returns

RRtoolbox.lib.arrayops.convert module This module unlike common and basic array operations classifies just the from-to-conversions methods

class `RRtoolbox.lib.arrayops.convert.SimKeyPoint` (*args)
Simulates opencv keypoint (it allows manipulation, conversion and serialization of keypoints).

Note: Used for conversions and data persistence.

`RRtoolbox.lib.arrayops.convert.apply2kp_pairs` (*kp_pairs*, *kp1_rel*, *kp2_rel*, *func=None*)
Apply to *kp_pairs*.

Parameters

- **kp_pairs** – list of (kp1,kp2) pairs
- **kp1_rel** – x,y relation or function to apply to kp1
- **kp2_rel** – x,y relation or function to apply to kp2
- **func** – function to build new copy of keypoint

Returns transformed *kp_pairs*

`RRtoolbox.lib.arrayops.convert.cnt2pts` (*contours*)
Convert contours to points. (*cnt2pts*)

Parameters **contours** – array of contours (*cnt*) ([[x,y]] only for openCV)

Returns

Example:

```
contours = np.array([[0, 0]], [[1, 0]]) # contours
points = contour2points(contours)
print points # np.array([[0, 0], [1, 0]])
```

`RRtoolbox.lib.arrayops.convert.contour2points` (*contours*)
Convert contours to points. (*cnt2pts*)

Parameters **contours** – array of contours (*cnt*) ([[x,y]] only for openCV)

Returns

Example:

```
contours = np.array([[0, 0]], [[1, 0]]) # contours
points = contour2points(contours)
print points # np.array([[0, 0], [1, 0]])
```

`RRtoolbox.lib.arrayops.convert.conv3H4H` (*M*)
Convert a 3D transformation matrix (TM) to 4D TM.

Parameters **M** – Matrix

Returns 4D Matrix

`RRtoolbox.lib.arrayops.convert.dict2keyPoint` (*d*, *func=<built-in function KeyPoint>*)
`KeyPoint([x, y, _size[, _angle[, _response[, _octave[, _class_id]]]])` -> `<KeyPoint object>`

`RRtoolbox.lib.arrayops.convert.getSOpintRelation` (*source_shape*, *destine_shape*, *as-
Matrix=False*)

Return parameters to change scaled point to original point.

destine_domain = *relation***source_domain*

Parameters

- **source_shape** – image shape for source domain
- **destine_shape** – image shape for destine domain
- **asMatrix** – if true returns a Transformation Matrix H

Returns x, y coordinate relations or H if asMatrix is True

Note: Used to get relations to convert scaled points to original points of an Image.

RRtoolbox.lib.arrayops.convert.**invertH**(*H*)
 Invert Transformation Matrix.

Parameters *H* –

Returns

RRtoolbox.lib.arrayops.convert.**keyPoint2tuple**(*keypoint*)
 obj.angle, obj.class_id, obj.octave, obj.pt, obj.response, obj.size

RRtoolbox.lib.arrayops.convert.**points2contour**(*points*)
 Convert points to contours. (pts2cnt)

Parameters *points* – array of points ([x,y] for openCV, [y,x] for numpy)

Returns

Example:

```
points = np.array([[0, 0], [1, 0]]) # points
contours = points2contour(points)
print contours # np.array([[0, 0], [1, 0]])
```

RRtoolbox.lib.arrayops.convert.**points2vectors**(*pts, origin=None*)
 Convert points to vectors with respect to origin.

Parameters

- **pts** – array of points.
- **origin** – point of origin.

Returns vectors.

RRtoolbox.lib.arrayops.convert.**pts2cnt**(*points*)
 Convert points to contours. (pts2cnt)

Parameters *points* – array of points ([x,y] for openCV, [y,x] for numpy)

Returns

Example:

```
points = np.array([[0, 0], [1, 0]]) # points
contours = points2contour(points)
print contours # np.array([[0, 0], [1, 0]])
```

RRtoolbox.lib.arrayops.convert.**sh2oh**(*sH, osrc_sh, sscr_sh, odst_sh, sdst_sh*)
 Convert scaled transformation matrix (sH) to original (oH).

Parameters

- **sH** – scaled transformation matrix
- **osrc_sh** – original source’s shape
- **sscr_sh** – scaled source’s shape
- **odst_sh** – original destine’s shape
- **sdst_sh** – scaled destine’s shape

Returns

RRtoolbox.lib.arrayops.convert.**spairs2opairs** (*kp_pairs*, *osrc_sh*, *sscr_sh*, *odst_sh*,
sdst_sh, *func=None*)

Convert scaled kp_pairs to original kp_pairs.

Parameters

- **kp_pairs** – list of kp_pairs
- **osrc_sh** – original source’s shape
- **sscr_sh** – scaled source’s shape
- **odst_sh** – original destine’s shape
- **sdst_sh** – scaled destine’s shape
- **func** – function to build new copy of keypoint

Returns

RRtoolbox.lib.arrayops.convert.**spoint2opointfunc** (*source_shape*, *destine_shape*)

Return function with parameters to change scaled point to original point.

Parameters

- **source_shape** –
- **destine_shape** – shape of

Returns

Example:

```
forefunc = scaled2realfunc(imgf.shape,bgr.shape)
backfunc = scaled2realfunc(imgb.shape,back.shape)
p1fore = np.array([forefunc(i) for i in p1])
p2back = np.array([backfunc(i) for i in p2])
```

RRtoolbox.lib.arrayops.convert.**toTuple** (*obj*)

Converts recursively to tuple

Parameters *obj* – numpy array, list structure, iterators, etc.

Returns tuple representation obj.

RRtoolbox.lib.arrayops.convert.**translateQuadrants** (*quadrants*, *quadrantmap*={(0, 1):
‘up’, (-1, 1): ‘left-up’, (0, 0): ‘ori-
gin’, (-1, 0): ‘left’, (-1, -1): ‘left-
down’, (0, -1): ‘down’, (1, 0):
‘right’, (1, -1): ‘right-down’, (1, 1):
‘right-up’})

Convert quadrants into human readable data.

Parameters

- **quadrants** – array of quadrants.

- **quadrantmap** – dictionary map to translate quadrants. it is of the form:

```
{ (0,0):"origin", (1,0):"right", (1,1):"top-right", (0,1):"top", (-1,1):"top-left",
  (-1,0):"left", (-1,-1):"bottom-left", (0,-1):"bottom", (1,-1):"bottom-right"}
```

Returns list of translated quadrants.

RRtoolbox.lib.arrayops.convert.**tuple2keyPoint** (*points*, *func*=<built-in function Key-Point>)
 KeyPoint([x, y, _size[, _angle[, _response[, _octave[, _class_id]]]]) -> <KeyPoint object>

RRtoolbox.lib.arrayops.convert.**vectors2points** (*vecs*, *origin*=None)
 Convert points to vectors with respect to origin.

Parameters

- **vecs** – array of vectors.
- **origin** – point of origin.

Returns points.

RRtoolbox.lib.arrayops.filters module This module contains custom 1D and 2D-array filters and pre-processing (as in filtering phase) methods

class RRtoolbox.lib.arrayops.filters.**BilateralParameters** (*d*=None, *sigmaColor*=None, *sigmaSpace*=None)

Bases: object

create instance to calculate bilateral parameters from image shape.

d -> inf then:

- computation is slower
- filtering is better to eliminate noise
- images look more cartoon-like

Parameters

- **d** – distance
- **sigmaColor** – sigma in color
- **sigmaSpace** – sigma in space

d = <RRtoolbox.lib.arrayops.filters.bilateraP object>

filters

list of filters

sigmaColor = <RRtoolbox.lib.arrayops.filters.bilateraP object>

sigmaSpace = <RRtoolbox.lib.arrayops.filters.bilateraP object>

class RRtoolbox.lib.arrayops.filters.**FilterBase** (*alpha*=None, *beta1*=None, *beta2*=None)

Bases: object

base filter to create custom filters

alpha

beta1

beta2

class `RRtoolbox.lib.arrayops.filters.bandpass` (*alpha*, *beta1*, *beta2*)

Bases: `RRtoolbox.lib.arrayops.filters.FilterBase`

bandpass filter

class `RRtoolbox.lib.arrayops.filters.bandstop` (*alpha*, *beta1*, *beta2*)

Bases: `RRtoolbox.lib.arrayops.filters.FilterBase`

bandstop filter

class `RRtoolbox.lib.arrayops.filters.bilateraP` (*scale*, *shift*=33, *name*=None, *alpha*=100,
beta1=-400, *beta2*=200)

Bases: `RRtoolbox.lib.arrayops.filters.bandstop`

bilateral parameter

`RRtoolbox.lib.arrayops.filters.bilateralFilter` (*im*, *d*, *sigmaColor*, *sigmaSpace*)

Apply bilateral Filter.

Parameters

- **im** –
- **d** –
- **sigmaColor** –
- **sigmaSpace** –

Returns filtered image

`RRtoolbox.lib.arrayops.filters.filterFactory` (*alpha*, *beta1*, *beta2*=None)

Make filter.

Parameters

- **alpha** – steepness of filter
 - **beta1** – first shift from origin
 - **beta2** – second shift from origin:
alpha must be != 0 if beta2 = None:
if alpha > 0: high-pass filter, if alpha < 0: low-pass filter
- else:**
- if beta2 > beta1:** if alpha > 0: band-pass filter, if alpha < 0: band-stop filter
 - else:** if alpha > 0: inverted-band-pass filter, if alpha < 0: inverted-band-stop filter

Returns filter funtion with intup levels

Example:

```
alpha,beta1,beta2 = 10,20,100
myfilter = filter(alpha,beta1,beta2)
print myfilter,type(myfilter)
print myfilter.alpha,myfilter.beta1,myfilter.beta2
```

`RRtoolbox.lib.arrayops.filters.getBilateralParameters` (*shape*, *mode*=None)

Calculate from shape bilateral parameters.

Parameters

- **shape** – image shape
- **mode** –

Returns

class `RRtoolbox.lib.arrayops.filters.highpass(alpha, beta1)`

Bases: `RRtoolbox.lib.arrayops.filters.FilterBase`

highpass filter

class `RRtoolbox.lib.arrayops.filters.invertedbandpass(alpha, beta1, beta2)`

Bases: `RRtoolbox.lib.arrayops.filters.bandpass`

inverted bandpass filter

class `RRtoolbox.lib.arrayops.filters.invertedbandstop(alpha, beta1, beta2)`

Bases: `RRtoolbox.lib.arrayops.filters.bandstop`

inverted bandstop filter

class `RRtoolbox.lib.arrayops.filters.lowpass(alpha, beta1)`

Bases: `RRtoolbox.lib.arrayops.filters.FilterBase`

lowpass filter

`RRtoolbox.lib.arrayops.filters.normsigmoid(x, alpha, beta)`

Apply normalized sigmoid filter.

Parameters

- **x** – data to apply filter
- **alpha** – if alpha > 0: pass high filter, if alpha < 0: pass low filter, alpha must be != 0
- **beta** – shift from origin

Returns filtered values normalized to range [-1 if x<0, 1 if x>=0]

`RRtoolbox.lib.arrayops.filters.sigmoid(x, alpha, beta, max=255, min=0)`

Apply sigmoid filter.

Parameters

- **x** – data to apply filter
- **alpha** – if alpha > 0: pass high filter, if alpha < 0: pass low filter, alpha must be != 0
- **beta** – shift from origin
- **max** – maximum output value
- **min** – minimum output value

Returns filtered values ranging as [min,max]

Note: Based from http://www.itk.org/Doxygen/html/classitk_1_1SigmoidImageFilter.html

`RRtoolbox.lib.arrayops.filters.smooth(x, window_len=11, window='hanning', correct=False)`

Smooth the data using a window with requested size.

This method is based on the convolution of a scaled window with the signal. The signal is prepared by introducing reflected copies of the signal (with the window size) in both ends so that transient parts are minimized in the beginning and end part of the output signal.

input: *x*: the input signal *window_len*: the dimension of the smoothing window; should be an odd integer
window: the type of window from 'flat', 'hanning', 'hamming', 'bartlett', 'blackman'

flat window will produce a moving average smoothing.

output: the smoothed signal

Example:

```
t=linspace(-2,2,0.1)
x=sin(t)+randn(len(t))*0.1
y=smooth(x)
```

See also:

numpy.hanning, numpy.hamming, numpy.bartlett, numpy.blackman, numpy.convolve, scipy.signal.lfilter

Note: `length(output) != length(input)`, to correct this: `return y[(window_len/2-1):-(window_len/2)]` instead of just `y`.

RRtoolbox.lib.arrayops.mask module This module contains all basic masking and pre-processing (as in segmenting phase) methods

`RRtoolbox.lib.arrayops.mask.background(gray, mask=None, iterations=3)`
get the background mask of a gray image. (this is the inverted of `foreground()`)

Parameters

- **gray** – gray image
- **mask** – (None) input mask to process gray
- **iterations** – (3) number of iterations to detect background with otsu threshold.

Returns output mask

`RRtoolbox.lib.arrayops.mask.biggestCnt(contours)`
Filters contours to get biggest contour.

Parameters *contours* –

Returns cnt

`RRtoolbox.lib.arrayops.mask.biggestCntData(contours)`
Gets index and area of biggest contour.

Parameters *contours* –

Returns index, area

`RRtoolbox.lib.arrayops.mask.brightness(img)`
get brightness from an image :param img: BGR or gray image :return:

`RRtoolbox.lib.arrayops.mask.cnt_hist(gray)`
Mask of an ellipse enclosing retina using histogram threshold.

Parameters

- **gray** – gray image

- **invert** – invert mask

Returns mask

`RRtoolbox.lib.arrayops.mask.foreground(gray, mask=None, iterations=3)`
get the foreground mask of a gray image. (this is the inverted of `background()`)

Parameters

- **gray** – gray image
- **mask** – (None) input mask to process gray
- **iterations** – (3) number of iterations to detect foreground with otsu threshold.

Returns output mask

`RRtoolbox.lib.arrayops.mask.gethull(contours)`
Get convex hull.

Parameters **contours** – contours or mask array

Returns cnt

`RRtoolbox.lib.arrayops.mask.hist_cdf(img, window_len=0, window='hanning')`
Get image histogram and the normalized cumulative distribution function.

Parameters

- **img** – image
- **window_len** –
- **window** –

Returns histogram (int), normalized cdf (float)

`RRtoolbox.lib.arrayops.mask.mask_watershed(BGR, GRAY=None)`
Get retinal mask with watershed method.

Parameters

- **BGR** –
- **GRAY** –

Returns mask

`RRtoolbox.lib.arrayops.mask.multiple_otsu(gray, mask=None, flag=0L, iterations=1)`
get the mask of a gray image applying Otsu threshold.

Parameters

- **gray** – gray image
- **mask** – (None) input mask to process gray
- **iterations** –
 1. number of iterations to detect Otsu threshold.

Returns thresh, mask

`RRtoolbox.lib.arrayops.mask.thresh_biggestCnt(thresh)`
From threshold obtain biggest contour.

Parameters **thresh** – binary image

Returns cnt

`RRtoolbox.lib.arrayops.mask.thresh_hist(gray)`

Get best possible thresh to threshold object from the gray image.

Parameters `gray` – gray image.

Returns thresh value.

`RRtoolbox.lib.arrayops.mask.threshold_opening(src, thresh, maxval, type)`

Eliminate small objects from threshold.

Parameters

- `src` –
- `thresh` –
- `maxval` –
- `type` –

Returns

Module contents

Submodules

RRtoolbox.lib.cache module

platform Unix, Windows

synopsis Serialize and Memoize.

Contains memoizing, caching, serializing and memory-mapping methods so as to let the package save its state (persistence) and to let a method “remember” what it processed in a session (with cache) or between sessions (memoization and serialization) of the same input contend once processed. It also wraps mmappping functions to let objects “live” in the disk (slower but almost unlimited) rather than in memory (faster but limited).

`@cache` is used as replacement of `@property` to compute a class method once. It is computed only one time after which an attribute of the same name is generated in its place.

`@cachedProperty` is used as replacement of `@property` to compute a class method depending on changes in its watched variables.

`@memoize` used as a general memoizer decorator for functions where metadata is generated to disk for persistence.

Made by Davto, powered by joblib. Dependent project: <https://github.com/joblib/joblib>

```
class RRtoolbox.lib.cache.DynamicMemoizedFunc(func, cachedir=None, ignore=None,
                                              mmap_mode=None, compress=False, ver-
                                             bose=1, timestamp=None, banned=False)
```

Bases: object

cachedir

call_and_shelve (*args, **kwargs)

clear (warn=True)

compress

enabled

func

ignore**mmap_mode****verbose****class** RRtoolbox.lib.cache.**Memoizer** (*ignore=()*, *ignoreAll=False*)

Bases: object

ignore**makememory** (*cachedir=None*, *mmap_mode=None*, *compress=False*, *verbose=0*)Make memory for `memoize()` decorator.**Parameters**

- **cachedir** – path to save metadata, if left None function is not cached.
- **mmap_mode** – {None, 'r+', 'r', 'w+', 'c'}, optional. The memmapping mode used when loading from cache numpy arrays. See `numpy.load` for the meaning of the arguments.
- **compress** – (boolean or integer) Whether to zip the stored data on disk. If an integer is given, it should be between 1 and 9, and sets the amount of compression. Note that compressed arrays cannot be read by memmapping.
- **verbose** – (int, optional) Verbosity flag, controls the debug messages that are issued as functions are evaluated.

Returns**memoize** (*memory=None*, *ignore=None*, *verbose=0*, *mmap_mode=False*)

Decorated functions are faster by trading memory for time, only hashable values can be memoized.

Parameters

- **memory** – (Memory or path to folder) if left None function is not cached.
- **ignore** – (list of strings) A list of arguments name to ignore in the hashing.
- **verbose** – (integer) Verbosity flag, controls the debug messages that are issued as functions are evaluated.
- **mmap_mode** – {None, 'r+', 'r', 'w+', 'c'}, optional. The memmapping mode used when loading from cache numpy arrays. See `numpy.load` for the meaning of the arguments.

Returns decorator**memoizers** = {140007976996752: <weakref at 0x7f5625b78520; to 'Memoizer' at 0x7f5625bc0f90>}**class** RRtoolbox.lib.cache.**MemorizedFunc** (*func*, *cachedir*, *ignore=None*, *mmap_mode=None*, *compress=False*, *verbose=1*, *timestamp=None*)Bases: `joblib.memory.MemorizedFunc`**class** RRtoolbox.lib.cache.**Memory** (*cachedir*, *mmap_mode=None*, *compress=False*, *verbose=1*)Bases: `joblib.memory.Memory`A wrapper to `joblib.Memory` to have better control.**class** RRtoolbox.lib.cache.**NotMemorizedFunc** (*func*)Bases: `joblib.memory.NotMemorizedFunc`**class** RRtoolbox.lib.cache.**cache** (*func*)

Bases: object

Descriptor (non-data) for building an attribute on-demand at first use. @cache decorator is used for class methods without inputs (only self reference to the object) and it caches on first compute. ex:

```
class x(object):
    @cache
    def method_x(self):
        return self.data
```

Note: Cached data can be deleted in the decorated object to recalculate its value.

RRtoolbox.lib.cache.**cachedProperty** (*watch=[]*, *handle=[]*)

A memoize decorator of @property decorator specifying what to trigger caching.

Parameters

- **watch** – (list of strings) A list of arguments name to watch in the hashing.
- **handle** – (list of handles or empty list) Provided list is appended with the memo handle were data is stored for the method and where a clear() function is provided.

Returns

RRtoolbox.lib.cache.**mapper** (*path*, *obj=None*, *mode=None*, *onlynumpy=False*)

Save and load or map live objects to disk to free RAM memory.

Parameters

- **path** – path to save mapped file.
- **obj** – the object to map, if None it tries to load obj from path if exist
- **mode** – {None, 'r+', 'r', 'w+', 'c'}.
- **onlynumpy** – if True, it saves a numpy mapper from obj.

Returns mmap image, names of mmap files

class RRtoolbox.lib.cache.**memoizedDict** (*path*, *mode=None*)

Bases: _abcoll.MutableMapping

memoized dictionary with keys and values persisted to files.

Parameters

- **path** – path to save memo file
- **mode** – loading mode from memo file {None, 'r+', 'r', 'w+', 'c'}

Warning: Some data structures cannot be memoize, so this structure is not save yet. Use at your own risk.

clear()

Remove all items from D.

exception RRtoolbox.lib.cache.**notCallable**

Bases: exceptions.Exception

Defines objectGetter error: given object is not callable.

exception RRtoolbox.lib.cache.**notCreatable**

Bases: exceptions.Exception

Defines objectGetter error: objectGetter cannot create new object.

class RRtoolbox.lib.cache.**objectGetter** (*callfunc=None*, *obj=None*, *callback=None*, ***annotations*)

Bases: object

Creates or get instance object depending if it is alive.

create (*throw=False*)

Creates an object and keep reference.

Parameters **throw** – if there is not creation function throws error.

Returns created object.

Warning: previous object reference is lost even if it was alive.

Note: Recommended only to use when object from current reference is dead.

getObj (*throw=False*)

isAlive ()

test if object of reference is alive

isCreatable ()

test if can create object

isGettable ()

test if object can be gotten either by reference or creation.

raw ()

get object from reference. :return: None if object is dead, object itself if is alive.

update (***kwargs*)

class `RRtoolbox.lib.cache.resourceManager` (*maxMemory=None, margin=0.8, unit='MB', all=True*)

Bases: `RRtoolbox.lib.cache.retriever`

keep track of references, create objects on demand, manage their memory and optimize for better performance.

Parameters

- **maxMemory** – (None) max memory in specified unit to keep in check optimization (it does not mean that memory never surpasses maxMemory).
- **margin** – (0.8) margin from maxMemory to trigger optimization. It is in percentage of maxMemory ranging from 0 (0%) to maximum 1 (100%). So optimal memory is inside range: $\text{maxMemory} * \text{margin} < \text{Memory} < \text{maxMemory}$
- **unit** – (MB) maxMemory unit, it can be GB (Gigabytes), MB (Megabytes), B (bytes)
- **all** – if True used memory is from all alive references, if False used memory is only from keptAlive references.

all

Returns all flag, if True: used memory is from all alive references, if False: used memory is only from keptAlive references.

bytes2units (*value*)

converts value from bytes to user units

getsizeof (*item*)

keepAlive (*key, obj*)

margin

Returns margin used for triggering memory optimization from maxMemory.

maxMemory

optimizeObject (*key, getter, toWhiteList=False*)

register (*key, method=None, instance=None*)

Register object to retrieve.

Parameters

- **key** – hashable key to retrieve
- **method** – callable method to get object
- **instance** – object instance already created from method

Note: This method is used in `__setitem__` as `self.register(key, value)`. Overwrite this method to change key assignation behaviour.

Example:

```
def mymethod():
    class constructor: pass
    return constructor()

ret = retriever()
ret["obj"] = mymethod # register creating method in "obj"
im = ret["obj"] # get object (created obj +1, with reference)
assert im is ret["obj"] # check that it gets the same object
# it remembers that "obj" is last registered or fetched object too
assert ret() is ret()
# lets register with better control (created obj2 +1, no reference)
ret.register("obj2",mymethod(),mymethod)
# proves that obj2 is not the same as obj (created obj2 +1, no reference)
assert ret() is not ret["obj"]
print list(ret.iteritems()) # get items
```

static resetGetter (*getter*)

Helper function to reset getter parameters.

Parameters **getter** – any instance of objectGetter

unit

Returns user defined units

units2bytes (*value*)

converts value from user units two bytes

usedMemory

Returns used memory in user units

class `RRtoolbox.lib.cache.retriever`

Bases: `_abcoll.MutableMapping`

keep track of references and create objects on demand if needed.

register (*key, method=None, instance=None*)

Register object to retrieve.

Parameters

- **key** – hashable key to retrieve
- **method** – callable method to get object
- **instance** – object instance already created from method

Returns

Example:

```
def mymethod():
    class constructor: pass
    return constructor()

ret = retriever()
ret["obj"] = mymethod # register creating method in "obj"
im = ret["obj"] # get object (created obj +1, with reference)
assert im is ret["obj"] # check that it gets the same object
# it remembers that "obj" is last registered or fetched object too
assert ret() is ret()
# lets register with better control (created obj2 +1, no reference)
ret.register("obj2",mymethod(),mymethod)
# proves that obj2 is not the same as obj (created obj2 +1, no reference)
assert ret() is not ret["obj"]
print list(ret.iteritems()) # get items
```

RRtoolbox.lib.config module

platform Unix, Windows

synopsis Looking for a reference? look here!.

This module contains all config data to the package.

class RRtoolbox.lib.config.**ConfigTool**
Manage the configured Tools.

static **getTools** (*package*)
Obtains the tools of a directory for the RRtoolbox.

Parameters **package** – path to the directory or package object.

Returns a dictionary of imported modules.

class RRtoolbox.lib.config.**directoryManager** (*path=None, raiseError=True, autosave=False*)
Bases: object

Manage the configured variables, paths and files.

Parameters

- **path** – (None) path to configuration file. If None uses default path.
- **raiseError** – True to raise when not attribute in ConfigFile.
- **autosave** – (True) if True saves at each change.

Note: Any attribute that is not in ConfigFile returns None. Use raiseError to control this behaviour.

default

get directories from dictionary representing environment variables.

Returns dictionary of directories.

Note: Only directories in the scope of the module are detected.

load()

loads the configuration file and update.

Returns loaded configuration file dictionary.

Warning: Unsaved instance variables will be replaced by configuration file variables.

reset()

Returns the configuration file to default variables.

Returns False, if error. Dictionary of new data, if successful.

Warning: All custom data is lost in configuration file.

Warning: ConfigFile is purposely not updated. Call manually method load()

save(mode=0)

saves configuration file.

Parameters **mode** – 0- delete and save, 1- update without replace, 2- update replacing variables.

Returns False, if error. Dictionary of new data, if successful.

`RRtoolbox.lib.config.findModules(package, exclude=None)`

Find modules from a package.

Parameters

- **package** – imported packaged or path (str).
- **exclude** – list of modules to exclude.

Returns dictionary containing importer, ispkg

`RRtoolbox.lib.config.getModules(package, exclude=None)`

Import modules from a package.

Parameters **package** – imported packaged or path (str).

Returns dictionary containing imported modules.

`RRtoolbox.lib.config.getPackagePath(package)`

Get the path of a package object.

Parameters **package** – package object or path (str).

Returns path to the package.

RRtoolbox.lib.descriptors module

`RRtoolbox.lib.descriptors.ASIFT(feature_name, img, mask=None, pool=<multiprocessing.pool.ThreadPool object>)`
`asift(feature_name, img, mask=None, pool=None) -> keypoints, descrs`

Apply a set of affine transformations to the image, detect keypoints and reproject them into initial image coordinates. See http://www.ipol.im/pub/algo/my_affine_sift/ for the details.

ThreadPool object may be passed to speedup the computation.

Parameters

- **feature_name** – feature name to create detector.
- **img** – image to find keypoints and its descriptors
- **mask** – mask to detect keypoints (it uses default, mask[:] = 255)
- **pool** – multiprocessing pool (dummy, it uses multithreading)

Returns keypoints, descriptors

`RRtoolbox.lib.descriptors.ASIFT_iter (imgs, feature_name='sift-flann')`
Affine-SIFT for N images.

Parameters

- **imgs** – images to apply asift
- **feature_name** – eg. SIFT SURF ORB

Returns [(kp1, desc1), ..., (kpN, descN)]

`RRtoolbox.lib.descriptors.ASIFT_multiple (imgs, feature_name='sift-flann')`
Affine-SIFT for N images.

Parameters

- **imgs** – images to apply asift
- **feature_name** – eg. SIFT SURF ORB

Returns [(kp1, desc1), ..., (kpN, descN)]

class `RRtoolbox.lib.descriptors.Feature (pool=<multiprocessing.pool.ThreadPool object>, useASIFT=True, debug=True)`

Bases: object

Class to manage detection and computation of features

Parameters

- **pool** – multiprocessing pool (dummy, it uses multithreading)
- **useASIFT** – if True adds Affine perspectives to the detector.
- **debug** – if True prints to the stdout debug messages.

config (name, separator='-')

This function takes parameters from a command to initialize a detector and matcher.

Parameters

- **name** – “[a-]<siftlsurflorb>[-flann]” (str) Ex: “a-sift-flann”
- **features** – it is a dictionary containing the mapping from name to the initialized detector, matcher pair. If None it is created. This feature is to reduce time by reusing created features.

Returns detector, matcher

detectAndCompute (img, mask=None)
detect keypoints and descriptors

Parameters

- **img** – image to find keypoints and its descriptors
- **mask** – mask to detect keypoints (it uses default, mask[:] = 255)

Returns keypoints, descriptors

`RRtoolbox.lib.descriptors.MATCH` (*feature_name, kp1, desc1, kp2, desc2*)

Use matcher and asift output to obtain Transformation matrix (TM).

Parameters

- **feature_name** – feature name to create detector. It is the same used in the detector which is used in `init_feature` function but the detector itself is ignored. e.g. if 'detector' uses BFMatcher, if 'detector-flann' uses FlannBasedMatcher.
- **kp1** – keypoints of source image
- **desc1** – descriptors of kp1
- **kp2** – keypoints of destine image
- **desc2** – descriptors of kp2

Returns TM

http://docs.opencv.org/3.0-beta/doc/py_tutorials/py_feature2d/py_feature_homography/py_feature_homography.html

`RRtoolbox.lib.descriptors.MATCH_multiple` (*pairlist, feature_name='sift-flann'*)

Parameters

- **pairlist** – list of keypoint and descriptors pair e.g. [(kp1, desc1), ..., (kpN, descN)]
- **feature_name** – feature name to create detector

Returns [(H1, mask1, kp_pairs1), ..., (HN, maskN, kp_pairsN)]

`RRtoolbox.lib.descriptors.affine_skew` (*tilt, phi, img, mask=None*)

Increase robustness to descriptors by calculating other invariant perspectives to image.

Parameters

- **tilt** – tilting of image
- **phi** – rotation of image (in degrees)
- **img** – image to find Affine transforms
- **mask** – mask to detect keypoints (it uses default, mask[:] = 255)

Returns skew_img, skew_mask, Ai (invert Affine Transform)

Ai - is an affine transform matrix from skew_img to img

`RRtoolbox.lib.descriptors.filter_matches` (*kp1, kp2, matches, ratio=0.75*)

This function applies a ratio test.

Parameters

- **kp1** – raw keypoints 1
- **kp2** – raw keypoints 2
- **matches** – raw matches
- **ratio** – filtering ratio of distance

Returns filtered keypoint 1, filtered keypoint 2, keypoint pairs

`RRtoolbox.lib.descriptors.init_feature(name, features=None)`

This function takes parameters from a command to initialize a detector and matcher.

Parameters

- **name** – “<siftlsurflorb>[-flann]” (str) Ex: “sift-flann”
- **features** – it is a dictionary containing the mapping from name to the initialized detector, matcher pair. If None it is created. This feature is to reduce time by reusing created features.

Returns detector, matcher

`RRtoolbox.lib.descriptors.inlineRatio(inlines, lines, thresh=30)`

Probability that a match was correct.

Parameters

- **inlines** – number of matched lines
- **lines** – number lines
- **thresh** – threshold for lines (i.e. very low probability \leq thresh < good probability)

Returns

RRtoolbox.lib.directory module

This module holds all path manipulation methods and a string concept called directory (referenced paths and strings) designed to support `config` and be used with `session`.

keywords:

path: it can be to a folder or file or url if specified *filename*: the file name without its path *filepath*: the path to a file *dirname*: the path to a folder *url*: Universal Resource Locator

class `RRtoolbox.lib.directory.FileDirectory`

Bases: `RRtoolbox.lib.directory.directory`

Saves contents of a file as with directories.

Parameters

- **data** – list, directory instance, dictionary or string.
- **filename** – name of file.
- **path** – path to folder where file is (it must finish in /).
- **notes** – optional description string
- **kwargs** – additional data to add in directory.

makeFile()

Makes a file with its contents to path/filename.

Returns True if successful

`RRtoolbox.lib.directory.changedir(filepath, dirname, ext=True)`

Change path to file with dirname.

Parameters

- **filepath** – path to file.

- **dirname** – new path to replace in filepath.
- **ext** – True to keep extension of file if any.

Returns directory object of changed path.

`RRtoolbox.lib.directory.checkDir(dirname)`
checks if dirname exists.

Parameters **dirname** – path to folder

Returns True if exists, False if not

`RRtoolbox.lib.directory.checkFile(path)`
checks if filepath or filename exists.

Parameters **path** – filepath or filename

Returns True if exists, False if not

`RRtoolbox.lib.directory.checkPath(path)`
checks if path exists.

Parameters **path** – path to folder or file.

Returns True if exists, False if not

`RRtoolbox.lib.directory.checkURL(url)`
checks if url exists. :param url: path to url :return: True if exists, False if not

`RRtoolbox.lib.directory.correctPath(path, relative)`
Get path corrected from its relative path or level index.

Parameters

- **path** – path or file name.
- **relative** – pattern or level in directory.

Returns corrected path.

`RRtoolbox.lib.directory.correctSep(path='/mnt/4E443F99443F82AF/Dropbox/PYTHON/RRtools/RRtoolbox/lib/direct', separator='/')`

Replaces the path separators by custom or OS standard separator.

Parameters

- **path** – relative or absolute path (str). Default is `__file__` or module's path.
- **separator** – desired separators, By default uses system separator (`os.path.sep`).

Returns path with corrected separator.

`RRtoolbox.lib.directory.decoratePath(relative, sep='/')`
Decorated path is controlled to give absolute path from relative path.

Parameters

- **relative** – int or path.
- **sep** – path separator

Returns decorator

class `RRtoolbox.lib.directory.directory`

Bases: `str`

semi-mutable string representation of a immutable string with support for path representations.

Parameters

- **data** – list, directory instance, dictionary or string.
- **ispath** – True to add support for paths.
- **copy** – when data is a directory if copy is True then this instance data is independent of the passed directory otherwise both directories are a reference to the same dictionary data but they are not the same object.
- **kwargs** – additional data to add in directory.

copy()

Creates copy of itself.

Returns non-referenced directory copy.

correctSTRBuiltin()

Decorate all the built-in functions of class directory.

Returns built-in decorated function.

static filterdata(data, ispath=None, kwargs=None)

Adequate data for dictionary creation.

Parameters

- **data** – any supported object.
- **ispath** – True to add support for paths.
- **kwargs** – additional data to add in directory.

Returns dictionary

static repr2list(data, level=0)

Converts the representation of a directory.repr to pickleable.

Parameters **data** – directory.repr of the form ["string",directory,...,directory.repr].

Returns pickleable list.

static repr2str(data, ispath=True)

Converts the representation of a directory.repr to string.

Parameters **data** – directory.repr of the form ["string",directory,...,directory.repr].

Returns converted string.

update(data=None)

Return an updated copy with provided data.

Parameters **data** – any supported object. If None return updated and referenced copy of itself.

Returns new directory referenced to itself.

update_left(other)

Updates representation a the left.

Parameters **other** – any supported object.

Returns new directory referenced to itself.

Note: Equivalent to self - other e.g. directory([other, self])

update_right (*other*)

Updates representation a the right.

Parameters *other* – any supported object.

Returns new directory referenced to itself.

Note: Equivalent to self + other e.g. directory([self, other])

RRtoolbox.lib.directory.**getData** (*path*='/mnt/4E443F99443F82AF/Dropbox/PYTHON/RRtools/RRtoolbox/lib/directory.p

Get standard path from path.

Parameters *path* – it can be to a folder or file. Default is __file__ or module's path.

Returns [drive,dirname,filename,ext]. 1. drive or UNC (Universal Naming Convention) 2. dirname is path to folder. 3. filename is name of file. 4. ext is extension of file.

RRtoolbox.lib.directory.**getFileHandle** (*path*)

Gets a file handle from url or disk file.

Parameters *path* – filepath or url

Returns file object

RRtoolbox.lib.directory.**getFileSize** (*path*)

Gets a size from url or disk file.

Parameters *path* – filepath or url

Returns size in bytes

RRtoolbox.lib.directory.**getPath** (*path*='/mnt/4E443F99443F82AF/Dropbox/PYTHON/RRtools/RRtoolbox/lib/directory.p

Get standard path from path.

Parameters *path* – it can be to a folder or file. Default is __file__ or module's path. If file exists it selects its folder.

Returns dirname (path to a folder)

Note: It is the same as os.path.dirname(os.path.abspath(path)).

RRtoolbox.lib.directory.**getSep** (*path*, *pattern*='\\')

Get path separator or indicator.

Parameters

- *path* – relative or absolute path (str).
- *pattern* – guess characters to compare path (str).

Returns sep (str).

Note: It is equivalent to os.path.sep but obtained from the given path and patterns.

RRtoolbox.lib.directory.**getShortenedPath** (*path*, *comp*)

Path is controlled to give absolute path from relative path or integer.

Parameters

- *path* – absolute path (str).

- **comp** – pattern or relative path (str) or integer representing level of folder determined by the separator Ex. “/level 1/level 2/.../level N or -1”.

Returns path before matched to comp Ex: “C://level 1//comp -> C://level 1”

Example:

```
>>> path = 'LEVEL1/LEVEL2/LEVEL3/LEVEL4/LEVEL5'
>>> print getShortenedPath(path,-2) # minus two levels
LEVEL1/LEVEL2/LEVEL3
>>> print getShortenedPath(path,2) # until three levels
LEVEL1/LEVEL2
>>> print getShortenedPath(path,'LEVEL1/LEVEL2/LEVEL3/')
LEVEL1/LEVEL2/LEVEL3/
>>> print getShortenedPath(path,'LEVEL4/REPLACE5/NEWLEVEL')
LEVEL1/LEVEL2/LEVEL3/LEVEL4/REPLACE5/NEWLEVEL
>>> print getShortenedPath(path,'../../SHOULD_BE_LEVEL4')
LEVEL1/LEVEL2/LEVEL3/SHOULD_BE_LEVEL4
```

`RRtoolbox.lib.directory.getSplitted (path='/mnt/4E443F99443F82AF/Dropbox/PYTHON/RRtools/RRtoolbox/lib/dire`
Splits a file path by its separators.

Parameters **path** – it can be to a folder or file. Default is `__file__` or module’s path.

Returns splitted path.

`RRtoolbox.lib.directory.increment_if_exists (fn, add='{num}')`
Generates new name if it exists.

Parameters

- **fn** – absolute path or filename
- **add** – if fn exists add pattern

Returns un-existent fn

`RRtoolbox.lib.directory.joinPath (absolute, relative)`
Joins an absolute path to a relative path.

Parameters

- **absolute** – directory or path.
- **relative** – directory or path.

Returns joined path.

Note: It is equivalent to `os.path.join` but works with directories.

`RRtoolbox.lib.directory.mkPath (path)`
Make path (i.e. creating folder) for filepath.

Parameters **path** – path to nonexistent folder or file.

Returns created path.

`RRtoolbox.lib.directory.quickOps (path, comp)`
(IN DEVELOPMENT) make quick matching operations in path.

Parameters

- **path** – path to folder

- **comp** – pattern

Returns

Requirements:

```
path = 'LEVEL1/LEVEL2/LEVEL3/LEVEL4/LEVEL5'
print quickOps(path, '../ROOT/../LEVEL1/../LEVEL2/LEVEL3/../../LEVEL4')
'LEVEL4'
print quickOps(path, 'ROOT/../LEVEL1/LEVEL2/../../LEVEL4')
'LEVEL3/LEVEL4'
print quickOps(path, '../LEVEL2/../../')
'LEVEL1/LEVEL3/LEVEL4/LEVEL5'
print quickOps(path, '../LEVEL2/../../')
'LEVEL1/LEVEL3/LEVEL4/LEVEL5/'
print quickOps(path, 'LEVEL2/../../LEVEL4/')
'LEVEL2/LEVEL3/LEVEL4/'
print quickOps(path, 'ROOT/../LEVEL2/../../LEVEL4')
'ROOT/LEVEL3/LEVEL4'
print quickOps(path, 'LEVEL-1/../../NEW7/LEVEL8')
'LEVEL-1/LEVEL1/LEVEL2/LEVEL3/LEVEL4/LEVEL5/NEW7/LEVEL8'
print
```

`RRtoolbox.lib.directory.resource_path` (*relative_path*='')
Get absolute path to resource, works for dev and for PyInstaller

`RRtoolbox.lib.directory.rmFile` (*filepath*)
Remove file.

Parameters *filepath* – path to file.

Returns None

`RRtoolbox.lib.directory.rmPath` (*path*, *ignore_errors=False*, *onerror=None*)
Remove path from path.

Parameters *path* – path to nonexistent folder or file.

Returns None

See also:

`shutil.rmtree`

`RRtoolbox.lib.directory.strdifference` (*s1*, *s2*)
Get string differences.

Parameters

- **s1** – string 1
- **s2** – string 2

Returns (splitted string 1, splitted string 2, index). A splitted string is a list with the string parts.
Index is a list containing the indexes of different parts of the two splitted strings.

RRtoolbox.lib.image module

Bundle of methods for handling images. Rather than manipulating specialized operations in images methods in this module are used for loading, outputting and format-converting methods, as well as color manipulation.

SUPPORTED FORMATS

see http://docs.opencv.org/2.4/modules/highgui/doc/reading_and_writing_images_and_video.html#imread

Windows bitmaps - *.bmp, *.dib (always supported) JPEG files - *.jpeg, *.jpg, *.jpe (see the Notes section) JPEG 2000 files - *.jp2 (see the Notes section) Portable Network Graphics - *.png (see the Notes section) Portable image format - *.pbm, *.pgm, *.ppm (always supported) Sun rasters - *.sr, *.ras (always supported) TIFF files - *.tiff, *.tif (see the Notes section)

RRtoolbox.lib.image.**bgra2bgr** (*im*, *bgrcolor*=(255, 255, 255))

Convert BGR to BGRA image.

Parameters

- **im** – image
- **bgrcolor** – BGR color representing transparency. (information is lost when converting BGRA to BGR) e.g. [200,200,200].

Returns

RRtoolbox.lib.image.**checkLoaded** (*obj*, *fn*='', *raiseError*=False)

Simple function to determine if variable is valid.

Parameters

- **obj** – loaded object
- **fn** – path of file
- **raiseError** – if True and obj is None, raise

Returns

None

RRtoolbox.lib.image.**convertAs** (*fns*, *base*=None, *folder*=None, *name*=None, *ext*=None, *overwrite*=False, *loader*=None, *simulate*=False)

Reads a file and save as other file based in a pattern.

Parameters

- **fns** – file name or list of file names. It supports glob operations. By default glob operations ignore folders.
- **base** – path to place images.
- **folder** – (None) folder to place images in base's path. If True it uses the folder in which image was loaded. If None, not folder is used.
- **name** – string for formatting new name of image with the {name} tag. Ex: if name is 'new_{name}' and image is called 'img001' then the formatted new image's name is 'new_img001'
- **ext** – (None) extension to save all images. If None uses the same extension as the loaded image.
- **overwrite** – (False) If True and the destine filename for saving already exists then it is replaced, else a new filename is generated with an index "{name}_{index}.{extension}"
- **loader** – (None) loader for the image file to change image attributes. If None reads the original images untouched.
- **simulate** – (False) if True, no saving is performed but the status is returned to confirm what images where adequately processed.

Returns list of statuses (0 - no error, 1 - image not loaded, 2 - image not saved, 3 - error in processing image)

RRtoolbox.lib.image.**drawcoorarea** (*vis*, *points*, *col_out*=(0, 0, 0), *col_in*=(0, 0, 255), *radius*=2)

Function to draw interaction with points to obtain area.

Parameters

- **vis** – image array.
- **points** – list of points.
- **col_out** – outer color of point.
- **col_in** – inner color of point.
- **radius** – radius of drawn points.

Returns

`RRtoolbox.lib.image.drawcooraxes` (*vis, points, col_out=(0, 0, 0), col_in=(0, 255, 0), radius=2*)

Function to draw axes instead of points.

Parameters

- **vis** – image array.
- **points** – list of points.
- **col_out** – outer color of point.
- **col_in** – inner color of point.
- **radius** – radius of drawn points.

Returns

`RRtoolbox.lib.image.drawcoorperspective` (*vis, points, col_out=(0, 0, 0), col_in=(0, 0, 255), radius=2*)

Function to draw interaction with points to obtain perspective.

Parameters

- **vis** – image array.
- **points** – list of points.
- **col_out** – outer color of point.
- **col_in** – inner color of point.
- **radius** – radius of drawn points.

Returns

`RRtoolbox.lib.image.drawcoorpoints` (*vis, points, col_out=(0, 0, 0), col_in=(0, 0, 255), radius=2*)

Function to draw points.

Parameters

- **vis** – image array.
- **points** – list of points.
- **col_out** – outer color of point.
- **col_in** – inner color of point.
- **radius** – radius of drawn points.

Returns

`RRtoolbox.lib.image.drawcoorpolyArrow` (*vis, points, col_out=(0, 0, 0), col_in=(0, 0, 255), radius=2*)

Function to draw interaction with vectors to obtain polygonal.

Parameters

- **vis** – image array.
- **points** – list of points.
- **col_out** – outer color of point.
- **col_in** – inner color of point.
- **radius** – radius of drawn points.

Returns

`RRtoolbox.lib.image.drawcoorpolyline(vis, points, col_out=(0, 0, 0), col_in=(0, 0, 255), radius=2)`

Function to draw interaction with points to obtain polygonal.

Parameters

- **vis** – image array.
- **points** – list of points.
- **col_out** – outer color of point.
- **col_in** – inner color of point.
- **radius** – radius of drawn points.

Returns

`RRtoolbox.lib.image.fig2bgr(fig)`

Convert a Matplotlib figure to a RGB image.

Parameters **fig** – a matplotlib figure

Returns RGB image.

`RRtoolbox.lib.image.fig2bgra(fig)`

Convert a Matplotlib figure to a RGBA image.

Parameters **fig** – a matplotlib figure

Returns RGBA image.

class `RRtoolbox.lib.image.getCoors(im, win='get coordinates', updatefunc=<function drawcoor-points>, unique=True, col_out=(0, 0, 0), col_in=(0, 0, 255))`

Bases: `RRtoolbox.lib.plotter.plotim`

Create window to select points from image.

Parameters

- **im** – image to get points.
- **win** – window name.
- **updatefunc** – function to draw interaction with points. (e.g. `limitaxispoints`, `drawcoor-perspective`, etc.).
- **prox** – proximity to identify point.
- **radius** – radius of drawn points.
- **unique** – If True no point can be repeated, else selected points can be repeated.
- **col_out** – outer color of point.
- **col_in** – inner color of point.

coors

drawstats (*points*, *col_out*=(0, 0, 0), *col_in*=(0, 255, 0), *radius*=2)

Parameters

- **self** –
- **points** –
- **col_out** –
- **col_in** –
- **radius** –

Returns

mousefunc ()

Parameters **self** –

Returns

updatecoors ()

Parameters **self** –

Returns

RRtoolbox.lib.image.**getcoors** (*im*, *win*='get coordinates', *updatefunc*=<function drawcoor-
points>, *coors*=None, *prox*=8, *radius*=3, *unique*=True, *col_out*=(0,
0, 0), *col_in*=(0, 0, 255))

RRtoolbox.lib.image.**getgeometrycoors** (**data*)

Get filled object coordinates. (function in progress)

RRtoolbox.lib.image.**getrectcoors** (**data*)

Get ordered points.

Parameters **data** – list of points

Returns [Top_left,Top_right,Bottom_left,Bottom_right]

RRtoolbox.lib.image.**gray2qi** (*gray*)

Convert the 2D numpy array *gray* into a 8-bit QImage with a gray colormap. The first dimension represents the vertical image axis.

ATTENTION: This QImage carries an attribute *ndimage* with a reference to the underlying numpy array that holds the data. On Windows, the conversion into a QPixmap does not copy the data, so that you have to take care that the QImage does not get garbage collected (otherwise PyQt will throw away the wrapper, effectively freeing the underlying memory - boom!).

source from: <https://kogs-www.informatik.uni-hamburg.de/~meine/software/vigraqt/qimage2ndarray.py>

RRtoolbox.lib.image.**hist_match** (*source*, *template*, *alpha*=None)

Adjust the pixel values of an image to match those of a template image.

Parameters

- **source** – image to transform colors to template
- **template** – template image ()
- **alpha** –

Returns transformed source

class RRtoolbox.lib.image.**imFactory** (**kwargs)

image factory for RRToolbox to create scripts to standardize loading images and provide lazy loading (it can load images from disk with the customized options and/or create mapping images to load when needed) to conserve memory.

Warning: In development.

get_Func ()

gets the loading function

get_code ()

get the script code

get_conversionFunc (code)

get_errorFunc (path=None, throw=None)

get_loadFunc (flag=None)

get_mapFunc (flag=None, RGB=None, mpath=None, mode=None, func=None, dsize=None, dst=None, fx=None, fy=None, interpolation=None)

get_np2qi ()

get_resizeFunc (dsize=None, dst=None, fx=None, fy=None, interpolation=None)

get_transposeFunc ()

update (**kwargs)

class RRtoolbox.lib.image.**imLoader** (path, flag=0, dsize=None, dst=None, fx=None, fy=None, interpolation=None, mmode=None, mpath=None, throw=True)

Class to load image array from path, url, server, string or directly from numpy array (supports databases).

Parameters

- **flag** – (default: 0) 0 to read as gray, 1 to read as BGR, -1 to read as BGRA, 2 to read as RGB, -2 to read as RGBA.

It supports openCV flags:

- cv2.CV_LOAD_IMAGE_COLOR
- cv2.CV_LOAD_IMAGE_GRAYSCALE
- cv2.CV_LOAD_IMAGE_UNCHANGED

value	openCV flag	output
2.	N/A	RGB
1.	cv2.CV_LOAD_IMAGE_COLOR	BGR
0.	cv2.CV_LOAD_IMAGE_GRAYSCALE	GRAYSCALE
(-1)	cv2.CV_LOAD_IMAGE_UNCHANGED	BGGR
(-2)	N/A	RGBA

- **dsize** – (None) output image size; if it equals zero, it is computed as:

```
exttt{dsize = Size(round(fx*src.cols), round(fy*src.rows))}
```

- **dst** – (None) output image; it has the size dsize (when it is non-zero) or the size computed from src.size(), fx, and fy; the type of dst is uint8.

- **fx** – scale factor along the horizontal axis; when it equals 0, it is computed as

```
exttt{(double)dsize.width/src.cols}
```

- **fy** – scale factor along the vertical axis; when it equals 0, it is computed as

```
exttt{(double)dsize.height/src.rows}
```

- **interpolation** – interpolation method compliant with opencv:

flag	Operation	Description
0.	INTER_NEAREST	nearest-neighbor interpolation
1.	INTER_LINEAR	bilinear interpolation (used by default)
2.	INTER_CUBIC	bicubic interpolation over 4x4 pixel neighborhood
3.	INTER_AREA	resampling using pixel area relation. It may be a preferred method for image decimation, as it gives moire'-free results. But when the image is zoomed, it is similar to the INTER_NEAREST method.
4.	INTER_LANCZOS4	Lanczos interpolation over 8x8 pixel neighborhood

- **mmode** – (None) mmode to create mapped file. if mpath is specified loads image, converts to mapped file and then loads mapping file with mode {None, 'r+', 'r', 'w+', 'c'} (it is slow for big images). If None, loads mapping file to memory (useful to keep image copy for session even if original image is deleted or modified).

- **mpath** – (None) path to create mapped file. None, do not create mapping file "", uses path directory; "*", uses working directory; else, uses specified directory.

Note: If mmode is None and mpath is given it creates mmap file but loads from it to memory. It is useful to create physical copy of data to keep loading from (data can be reloaded even if original file is moved or deleted).

getConfiguration (**kwargs)

get Custom configuration from default configuration :param kwargs: keys to customize default configuration.

If no key is provided default configuration is returned.

Returns dictionary of configuration

temp (**kwargs)

loads from temporal loader created with customized and default parameters.

Parameters **kwargs** – keys to customize default configuration.

Returns loaded image.

class RRtoolbox.lib.image.**imcoors** (pts, dtype=<type 'numpy.float32'>, deg=False)

Bases: object

Image's coordinates class. Example:

```
a = imcoors(np.array([(116, 161), (295, 96), (122, 336), (291, 286)]))
print a.__dict__
print "mean depend on min and max: ", a.mean
print a.__dict__
print "after mean max has been already been calculated: ", a.max
a.data = np.array([(116, 161), (295, 96)])
print a.__dict__
print "mean and all its dependencies are processed again: ", a.mean
```

dtype

pts

RRtoolbox.lib.image.**interpretImage** (toparse, flags)

Interprets to get image.

Parameters

- **toparse** – string to parse or array. It can interpret:
 - *connection to server (i.e. host:port)
 - *path to file (e.g. /path_to_image/image_name.ext)
 - *URL to image (e.g. http://domain.com/path_to_image/image_name.ext)
 - *image as string (i.g. numpy converted to string)
 - *image itself (i.e. numpy array)
- **flags** – openCV flags:

value	openCV flag	output
1.	cv2.CV_LOAD_IMAGE_COLOR	RGB
0.	cv2.CV_LOAD_IMAGE_GRAYSCALE	GRAYSCALE
(-1)	cv2.CV_LOAD_IMAGE_UNCHANGED	UNCHANGED

Returns image or None if not successful

RRtoolbox.lib.image.**limitaxispoints** (c, maxc, minc=0)

Limit a point in axis.

Parameters

- **c** – list of points..
- **maxc** – maximum value of point.
- **minc** – minimum value of point.

Returns return limited points.

`RRtoolbox.lib.image.loadFunc` (*flag=0, dsize=None, dst=None, fx=None, fy=None, interpolation=None, mmode=None, mpath=None, throw=True, keepratio=True*)

Creates a function that loads image array from path, url, server, string or directly from numpy array (supports databases).

Parameters

- **flag** – (default: 0) 0 to read as gray, 1 to read as BGR, -1 to read as BGRA, 2 to read as RGB, -2 to read as RGBA.

It supports openCV flags:

- `cv2.CV_LOAD_IMAGE_COLOR`
- `cv2.CV_LOAD_IMAGE_GRAYSCALE`
- `cv2.CV_LOAD_IMAGE_UNCHANGED`

value	openCV flag	output
2.	N/A	RGB
1.	<code>cv2.CV_LOAD_IMAGE_COLOR</code>	BGR
0.	<code>cv2.CV_LOAD_IMAGE_GRAYSCALE</code>	GRAYSCALE
(-1)	<code>cv2.CV_LOAD_IMAGE_UNCHANGED</code>	BGRA
(-2)	N/A	RGBA

- **dsize** – (None) output image size; if it equals zero, it is computed as:

`exttt{dsize = Size(round(fx*src.cols), round(fy*src.rows))}`

If (integer,None) or (None,integer) it completes the values according to `keepratio` parameter.

- **dst** – (None) output image; it has the size `dsize` (when it is non-zero) or the size computed from `src.size()`, `fx`, and `fy`; the type of `dst` is `uint8`.
- **fx** – scale factor along the horizontal axis
- **fy** – scale factor along the vertical axis
- **interpolation** – interpolation method compliant with `opencv`:

flag	Operation	Description
0.	INTER_NEAREST	nearest-neighbor interpolation
1.	INTER_LINEAR	bilinear interpolation (used by default)
2.	INTER_CUBIC	bicubic interpolation over 4x4 pixel neighborhood
3.	INTER_AREA	resampling using pixel area relation. It may be a preferred method for image decimation, as it gives moire'-free results. But when the image is zoomed, it is similar to the INTER_NEAREST method.
4.	INTER_LANCZOS4	Lanczos interpolation over 8x8 pixel neighborhood

- **mmode** – (None) mmode to create mapped file. if mpath is specified loads image, converts to mapped file and then loads mapping file with mode {None, 'r+', 'r', 'w+', 'c'} (it is slow for big images). If None, loads mapping file to memory (useful to keep image copy for session even if original image is deleted or modified).
- **mpath** – (None) path to create mapped file. None, do not create mapping file "", uses path directory; "*", uses working directory; else, uses specified directory.
- **keepratio** – True to keep image ratio when completing data from dsize,fx and fy, False to not keep ratio.

Note: If mmode is None and mpath is given it creates mmap file but loads from it to memory. It is useful to create physical copy of data to keep loading from (data can be reloaded even if original file is moved or deleted).

:return loader function

RRtoolbox.lib.image.**loadcv** (*path, flags=-1, shape=None*)

Simple function to load using opencv.

Parameters

- **path** – path to image.
- **flag** – openCV flags:

value	openCV flag	output
1.	cv2.CV_LOAD_IMAGE_COLOR	color
0.	cv2.CV_LOAD_IMAGE_GRAYSCALE	grayscale
(-1)	cv2.CV_LOAD_IMAGE_UNCHANGED	unchanged

- **shape** – shape to resize image.

Returns loaded image

```
class RRtoolbox.lib.image.loaderDict (loader=None,      maxMemory=None,      margin=0.8,
                                     unit='MB', all=True, config=None)
```

Bases: `RRtoolbox.lib.cache.resourceManager`

Class to standardize loading objects and manage memory efficiently.

Parameters

- **loader** – default loader for objects (e.g. load from file or create instance object)
- **maxMemory** – (None) max memory in specified unit to keep in check optimization (it does not mean that memory never surpasses maxMemory).
- **margin** – (0.8) margin from maxMemory to trigger optimization. It is in percentage of maxMemory ranging from 0 (0%) to maximum 1 (100%). So optimal memory is inside range: $\text{maxMemory} * \text{margin} < \text{Memory} < \text{maxMemory}$
- **unit** – (MB) maxMemory unit, it can be GB (Gigabytes), MB (Megabytes), B (bytes)
- **all** – if True used memory is from all alive references, if False used memory is only from keptAlive references.
- **config** – (Not Implemented)

register (*key*, *path=None*, *method=None*)

```
RRtoolbox.lib.image.loadsfrom (path, flags=IL)
```

Loads Image from URL or file.

Parameters

- **path** – filepath or url
- **flags** – openCV flags:

value	openCV flag	output
1.	cv2.CV_LOAD_IMAGE_COLOR	RGB
0.	cv2.CV_LOAD_IMAGE_GRAYSCALE	GRAY
(-1)	cv2.CV_LOAD_IMAGE_UNCHANGED	UNCHANGED

Returns

```
RRtoolbox.lib.image.myline (img, pt1, pt2, color, thickness=None)
```

Funtion to draw points (experimental).

Parameters

- **img** –
- **pt1** –
- **pt2** –
- **color** –
- **thickness** –

Returns

RRtoolbox.lib.image.**np2qi** (*array*)

Convert numpy array to Qt Image.

source from: <https://kogs-www.informatik.uni-hamburg.de/~meine/software/vigraqt/qimage2ndarray.py>

Parameters *array* –

Returns

RRtoolbox.lib.image.**np2str** (*arr*)

class RRtoolbox.lib.image.**pathLoader** (*fns=None, loader=None*)

Bases: `_abcoll.MutableSequence`

Class to standardize loading images from list of paths and offer lazy evaluations.

Parameters

- **fns** – list of paths
- **loader** – path loader (loadcv, loadsfrom, or function from loadFunc)

Example:

```
fns = ["/path to/image 1.ext", "/path to/image 2.ext"]
imgs = pathLoader(fns)
print imgs[0] # loads image in path 0
print imgs[1] # loads image in path 1
```

insert (*index, value*)

RRtoolbox.lib.image.**plt2bgr** (*image*)

RRtoolbox.lib.image.**plt2bgra** (*image*)

RRtoolbox.lib.image.**qi2np** (*qimage, dtype='array'*)

Convert QImage to numpy.ndarray. The dtype defaults to uint8 for QImage.Format_Indexed8 or *bgra_dtype* (i.e. a record array) for 32bit color images. You can pass a different dtype to use, or 'array' to get a 3D uint8 array for color images.

source from: <https://kogs-www.informatik.uni-hamburg.de/~meine/software/vigraqt/qimage2ndarray.py>

RRtoolbox.lib.image.**quadrants** (*points*)

Separate points respect to center of gravity point.

Parameters *points* – list of points

Returns [[Top_left],[Top_right],[Bottom_left],[Bottom_right]]

RRtoolbox.lib.image.**rgb2qi** (*rgb*)

Convert the 3D numpy array *rgb* into a 32-bit QImage. *rgb* must have three dimensions with the vertical, horizontal and RGB image axes.

ATTENTION: This QImage carries an attribute *ndimage* with a reference to the underlying numpy array that holds the data. On Windows, the conversion into a QPixmap does not copy the data, so that you have to take care that the QImage does not get garbage collected (otherwise PyQt will throw away the wrapper, effectively freeing the underlying memory - boom!).

source from: <https://kogs-www.informatik.uni-hamburg.de/~meine/software/vigraqt/qimage2ndarray.py>

RRtoolbox.lib.image.**separe** (*values, sep, axis=0*)

Separate values from separator or threshold.

Parameters

- **values** – list of values

- **sep** – separator value
- **axis** – axis in each value

:return:lists of greater values, list of lesser values

`RRtoolbox.lib.image.str2np(string, shape)`

`RRtoolbox.lib.image.transposeIm(im)`

`RRtoolbox.lib.image.try_loads(fns, func=<built-in function imread>, paths=None, debug=True)`

Try to load images from paths.

Parameters

- **fns** – list of file names
- **func** – loader function
- **paths** – paths to try. By default it loads working dir and test path
- **debug** – True to show debug messages

Returns image else None

RRtoolbox.lib.inspector module

This module is an all purpose intended for debugging, tracking, auto-documenting and self-introspecting the package

Made by DavtoH. Powered partially by pycallgraph. Dependent project: <https://github.com/gak/pycallgraph/#python-call-graph>

class `RRtoolbox.lib.inspector.Asyncronous(outputs, config)`

Bases: `RRtoolbox.lib.inspector.Synchronous`

done()

start()

tracer(frame, event, arg)

class `RRtoolbox.lib.inspector.Logger(**kwargs)`

Bases: `object`

Logger for decorated functions. Holds important information of an instanced object and can be used with `@trace` decorator for traceback purposes.

Parameters

- **func** – object reference.
- **funcname** – object name.
- **inputs** – inputs pass to the object.
- **outputs** – outputs given by the object execution.
- **time** – initial time of execution.
- **exectime** – time of execution in seconds.
- **writer** – writer function where messages are passed.
- **eventHandle** – event function where object is passed when `Logger.broadcast()` is called.
- **msg_report** – message format to use in reports.

- **msg_no_executed** – message format to pass to writer when object has not been executed and `Logger.report()` is called.
- **msg_executed** – message format to use when object is executed and `Logger.broadcast()` is called.

Time_
returns formatted time (str)

Type_
returns type name (str)

broadcast ()
pass a notification message on object execution to the writer

eventHandle = None

file = <open file ‘<stdout>’, mode ‘w’>

renew ()
renew Instance

report ()
pass a report of the last executed object to the writer

throwError ()
throw caught error :return:

tracer

writer (sender, *arg)

class `RRtoolbox.lib.inspector.Synchronous` (outputs, config)
Bases: `pycallgraph.tracer.SynchronousTracer`

start ()

stop ()

`RRtoolbox.lib.inspector.funcData` (func)

class `RRtoolbox.lib.inspector.graphTrace` (output=None, config=None)
Bases: `pycallgraph.pycallgraph.PyCallGraph`

get_tracer_class ()

saveSource (file)

source

class `RRtoolbox.lib.inspector.graphTraceOutput` (source=None, saveflag=True, label='',
**kwargs)

Bases: `pycallgraph.output.graphviz.GraphvizOutput`

done ()

save (file=None, source=None)

saveSource (file, source=None)

`RRtoolbox.lib.inspector.load` (mod_name, obj_name)
Convert a string version of a class name to the object.

For example, `get_class('sympy.core.Basic')` will return class `Basic` located in module `sympy.core`

`RRtoolbox.lib.inspector.reloadFunc` (func)

`RRtoolbox.lib.inspector.tracer` (*instance, broadcast=True, report=True*)
Tracer for decorated functions.

Parameters

- **instance** – Logger instance
- **broadcast** –
- **report** –

Returns

RRtoolbox.lib.plotter module

This module holds the plotting and data-visualization tools. Motto: don't know how it is interpreted? i'll show you!

```
#plotim example filename = "t2.jpg" win = "test" img = cv2.resize(cv2.imread(filename), (400, 400)) # (height, width)
plot = plotim(win,img) plot.show()
```

`RRtoolbox.lib.plotter.background` (*color, x=1, y=1, flag=0*)
Creates background rectangle.

Parameters

- **color** – main color.
- **x** – x pixels in axis x.
- **y** – y pixels in axis y.
- **flag** – Not implemented.

Returns image of shape y,x and ndim == color.ndim.

`RRtoolbox.lib.plotter.convert2bgr` (*src, bgrcolor=None*)
Tries to convert any image format to BGR.

Parameters

- **src** – source image.
- **bgrcolor** – background or transparent color.

Returns BGR array image.

`RRtoolbox.lib.plotter.convert2bgra` (*src, bgrcolor=None, transparency=None*)
Tries to convert any image format to BGRA.

Parameters

- **src** – source image.
- **bgrcolor** – background or transparent color.
- **transparency** – mask or A channel. (typically source image has not A channel, so user can provide it)

Returns BGRA array image.

`RRtoolbox.lib.plotter.echo` (*obj*)
Printer (used when user wants to print an object from plotim) :param obj: object

class `RRtoolbox.lib.plotter.edger` (*img, isSIZE=True, isEQUA=False, isCLAHE=False, isBFILTER=False*)
Bases: `RRtoolbox.lib.plotter.plotim`

Test visualization for edges

self.edge -> the edges in processed image self.img -> the processed image self.sample -> the rendered preprocessed image

```
computeAll()
computeEdge()
getParameters(params=('d', 'sigmaColor', 'sigmaSpace', 'clipLimit', 'tileGridSize', 'isSIZE', 'isEQUA', 'isCLAHE', 'isBFILTER', 'th1', 'th2', 'size', 'apertureSize', 'L2gradient'))
isActiveWindow()
isBFILTER
isCLAHE
isEQUA
isSIZE
load(img, compute=True)
maxth
onTrackbar1(*args)
onTrackbar2(*args)
save(strname=None, ext='.png', name='img')
showgray
size
th1
th2
windowfunc()
```

```
RRtoolbox.lib.plotter.fastplt(image, cmap=None, title='visualazor', win=None, block=False,
                              daemon=False)
```

Fast plot.

Parameters

- **image** – image to show
- **cmap** – “gray” or None
- **title** – title of subplot
- **win** – title of window
- **block** – if True it wait for window close, else it detaches (Experimental)
- **daemon** – if True window closes if main thread ends, else windows must be closed to main thread to end (Experimental)

Returns plt

```
RRtoolbox.lib.plotter.graph_filter(filters, levels=None, titles=None, win=None, single=True,
                                   legend=True, annotate=True, cols=3, scale=0.07,
                                   show=True, lxp=None, lyp=None)
```

Graph filter with standard data to watch response.

Parameters

- **filters** – list of filters
- **levels** – numpy array with values. if None tries to fit data or assumes from 0 to 255
- **titles** – list of titles for each filter in filters. if None creates the titles
- **win** – window name
- **single** – True to plot all filters in one plot. else separate each filter in a plot.
- **legend** – True to add legends.
- **annotate** – True to add annotations.
- **cols** – number of columns to create plots
- **scale** – factor from maximum to draw annotations
- **show** – to show the figure

Returns figure

class RRtoolbox.lib.plotter.**imtester** (*img*, *win*=*'imtester plot'*)

Bases: [RRtoolbox.lib.plotter.plotim](#)

Used to test some concepts as thresholds and filters

static applythresh (*img*, *type*, *adaptativetoggle*, *threshtoggle*, *th*, *blocksz*, *c*, *i*='', *ti*='', *info*='', *title*='')

builtcmd()

computefunc (*image*=None)

detectType (*type*, *i*='', *info*='')

static formatinfo (*info*, *words*=9)

updatevisualization (*image*, *channel*, *th*=None, *items*=None, *thresh1*=None, *thresh2*=None)

visualize()

windowfunc()

RRtoolbox.lib.plotter.**limitaxis** (*c*, *maxc*, *minc*=0)

Limit value in axis.

Parameters

- **c** – value
- **maxc** – max c value.
- **minc** – min c value.

Returns limited c value $c \in [\text{minc}, \text{maxc}]$

class RRtoolbox.lib.plotter.**matchExplorer** (*win*, *img1*, *img2*, *kp_pairs*=(), *status*=None, *H*=None, *show*=True, *block*=True, *daemon*=True)

Bases: [RRtoolbox.lib.plotter.plotim](#)

Draws a set of keypoint pairs obtained on a match method of a descriptor on two images *imgf* and *imgb*. (backend: *plotim*).

Parameters

- **win** – window's name (str)
- **img1** – image1 (numpy array)

- **img2** – image2 (numpy array)
- **kp_pairs** – zip(keypoint1, keypoint2)
- **status** – obtained from cv2.findHomography
- **H** – obtained from cv2.findHomography (default=None)
- **show** – if True shows plotim using block and daemon, else do not show
- **block** – if True it wait for window close, else it detaches
- **daemon** – if True window closes if main thread ends, else windows must be closed to main thread to end

Returns plotim object with visualization as self.rimg (image with matching result) (default=None)

Note: It supports BGR and gray images.

drawline()

Draws background visualization without interaction

drawrelation()

Draw keypoints where pointer is placed and pressed

keyfunc()

mousefunc()

static randomColor()

updaterenderer (*img=None, zoom=True*)

update renderer when called.

Parameters

- **img** – image to update in renderer, if None use self.img
- **zoom** – True to enable zoom, else updates with original img.

Returns None

RRtoolbox.lib.plotter.**plotPointsContour** (*pts, ax=None, lcor='k', pcor=None, deg=None, annotate=True, width=0.004, label='pt{pt}({x}, {y}, {a})', arrowprops=None*)

Plots points and joining lines in axes.

Parameters

- **pts** – points. [(x0,y0)...(xN,yN)]
- **ax** – axes handle to draw points.
- **lcor** – color of joining lines.
- **pcor** – color of points. If specified uses lines, else vectors.
- **deg** – angle of vertex, if True in degrees, if False in radians, if None do not add.

Returns ax.

class RRtoolbox.lib.plotter.**plotim** (*win, im=array([[1]]), bgrcolor=(250, 243, 238)*)

Bases: object

Show and image with events, animations, controls, internal commands and highly customizable by code.

Parameters

- **win** – window name
- **im** – image of numpy array
- **bgrcolor** – default color to use for transparent or background color.

Warning: plotim is deprecated and will be replaced in the future (it was made to test concepts). Originally it was made for windows but some functions were removed to let it be multi-platform.

builtincmd()

Internal cmd control

builtincontrol (*control=False*)

Internal control. use self.usecontrol = True to activate.

Parameters **control** – if True, use control key.

Returns

builtinplot (*pixel=None, useritems=None, flag=1, xpad=0, ypad=0, bgrcolor=None, alpha=None*)

Internal plot.

Parameters

- **pixel** – pixel color where mouse is placed (placed for better control). Color can be from real image, showed image, original image or rendered image, or any color.
- **useritems** – items to show.
- **flag** – flag for position (default=0).
 - flag==0 : foreground to left up.
 - flag==1 : foreground to left down.
 - flag==2 : foreground to right up.
 - flag==3 : foreground to right down.
 - flag==4 : foreground at center of background.
 - flag==5 : XY 0,0 is at center of background.
 - flag==6 : XY 0,0 is at center of foreground.
 - flag==7 : XY 0,0 is at right down of foreground.
- **xpad** – padding in x
- **ypad** – padding in y
- **bgrcolor** – background color
- **alpha** – alpha mask or value for transparency

Returns

builtinwindow()

loads windowfunc, showfunc, starts window thread and mousecallback.

clean()

Attempt to clean the plotter dictionary for an error in garbage collection. :return:

closefunc()

Decoupled close function for plotim (replace self.closefunc).

Parameters **self** – plotim instance

cmdfunc (*execute=False*)

command function and decoupled cmd solver for plotim. (replace self.cmdfunc)

Parameters

- **self** –
- **execute** – True, enable execution of commands, False, disable execution.

errorbackground

formatcmd (*cmd, references=('+', '-', '*', '='), lmissing='self'*)

Decoupled cmd formatter for cmdfunc and plotim.

Parameters

- **self** – plotim instance
- **cmd** – command
- **references** –
- **lmissing** – assumed missing part in command

Returns

help (*showAll=False*)

function to print the quick help for the user with all the commands

init ()

Pseudo `__init__`. it is used to restart default values without destroying configurations.

keyfunc ()

Decoupled key function for plotim (replace self.keyfunc).

Parameters **self** – plotim instance

makeoverlay (*items, xpad=0, ypad=0, bgrcolor=None, alpha=None*)

overlay items over image.

Parameters

- **self** – instance
- **items** – list of object to overlay
- **xpad** – pad in x
- **ypad** – pad in y
- **bgrcolor** – background color
- **alpha** – transparency color

Returns overlaid

mousefunc ()

Decoupled mouse function for plotim (replace self.mousefunc).

Parameters **self** – plotim instance

static onmouse (*event, x, y, flags, self*)

Mouse event function for plotim. (replace self.mousefunc)

Parameters

- **event** – mouse event
- **x** – x position

- **y** – y position
- **flags** – mouse flag to use in control (it represents clicks)
- **self** – plotim object

Returns

plotatpointer (*items, img=None, x=0, y=0, flag=6, xpad=0, ypad=0, bgrcolor=None, alpha=None, pixel=None*)

Plot message where mouse pointer is.

Parameters

- **items** – list of items supported by `self.makeoverlay()`
- **img** – image to place in items. If None it uses `self.remg`
- **x** – x position
- **y** – y position
- **flag** – flag for position (default=0).
 - `flag==0` : foreground to left up.
 - `flag==1` : foreground to left down.
 - `flag==2` : foreground to right up.
 - `flag==3` : foreground to right down.
 - `flag==4` : foreground at center of background.
 - `flag==5` : XY 0,0 is at center of background.
 - `flag==6` : XY 0,0 is at center of foreground.
 - `flag==7` : XY 0,0 is at right down of foreground.
- **xpad** – padding in x
- **ypad** – padding in y
- **bgrcolor** – background color
- **alpha** – alpha mask or value for transparency
- **pixel** – color to add as item in items,

Returns

plotatxy (*items, img=None, x=0, y=0, flag=0, xpad=0, ypad=0, bgrcolor=None, alpha=None*)

Plot message in xy position.

Parameters

- **items** – list of items supported by `makeoverlay()`
- **img** – image to place in items. If None it uses `self.remg`
- **x** – x position
- **y** – y position
- **flag** – flag for position (default=0).
 - `flag==0` : foreground to left up.
 - `flag==1` : foreground to left down.

- `flag==2` : foreground to right up.
- `flag==3` : foreground to right down.
- `flag==4` : foreground at center of background.
- `flag==5` : XY 0,0 is at center of background.
- `flag==6` : XY 0,0 is at center of foreground.
- `flag==7` : XY 0,0 is at right down of foreground.

- **xpad** – padding in x
- **ypad** – padding in y
- **bgrcolor** – background color
- **alpha** – alpha mask or value for transparency

Returns

plotintime (*items=None, wait=2, img=None, bgrcolor=None*)
plots messages and events.

Parameters

- **items** – list of items supported by `makeoverlay()`
- **wait** – time of message.
- **img** – image to place in items. If None it uses `self.remg`
- **bgrcolor** – color of message.

Returns

real2render (*x, y, astype=None*)
from real coordinates get rendered coordinates.

Parameters

- **x** – real x
- **y** – real y
- **astype** – (np.int32) return as the specified type

Returns rendered x, rendered y

render2real (*rx, ry, astype=<type 'numpy.int32'>*)
from rendered coordinates get real coordinates.

Parameters

- **rx** – rendered x
- **ry** – rendered y
- **astype** – (np.int32) return as the specified type

Returns real x, real y

rx1

rx2

ry1

ry2

save (*strname=None, ext='.png', name='img'*)

Save image (save image if not Qt backend is installed) :param strname: name to save, a label with {win} can be used to be replaced with the plot win name :param ext: (".png") extension. :param name: ("img") name of image object from self. default is "img" that is self.img

(it allows better control to get custom image)

Returns True if saved, False if not saved (possibly because folder does not exists)

show (*frames=None, block=True, daemon=False, clean=True*)

Show function. calls buildinwindow, handles key presses and close events.

Parameters

- **frames** – show number of frames and close.
- **block** – if True it wait for window close, else it detaches (Experimental)
- **daemon** – if True window closes if main thread ends, else windows must be closed to main thread to end (Experimental)

Returns

showfunc (*img=None*)

Decoupled show function for plotim (replace self.showfunc).

Parameters

- **self** – plotim instance
- **img** – image to show

textbackground

updaterenderer (*img=None, zoom=True*)

update renderer when called.

Parameters

- **img** – image to update in renderer, if None use self.img
- **zoom** – True to enable zoom, else updates with original img.

Returns None

windowfunc ()

Decoupled window function for plotim (replace self.windowfunc).

Parameters **self** – plotim instance

RRtoolbox.lib.root module

This module holds core-like methods for library modules but not for the hole package

class `RRtoolbox.lib.root.Controlstdout` (*disable=True, buffer=None*)

Bases: object

Context manager to control output to stdout

Parameters

- **disable** – if True suppress output.

- **buffer** – (None) if True creates a buffer to collect all data printed to the stdout which can be retrieved with `self.buffered`. A file can be given but if it is write-only it cannot retrieve data to `self.buffered` so “w+” is recommended to be used with `self.buffered`.

Warning: If a references to `sys.stdout` is kept before the `ControlStdout` instance then output can be printed trough it and cannot be controlled by the `ControlStdout` context.

class `RRtoolbox.lib.root.FactorConvert` (*factor=None, abbreviate=True*)

Bases: `object`

Keep track of factor and converts to any available factor.

convert (*factor, to=None*)

Convert from actual factor to another factor.

Parameters

- **factor** – number
- **to** – factor to convert

Returns converted value, units

convert2sample (*factor, to=None*)

Convert to resemble sample.

Parameters

- **factor** – number
- **to** – sample factor.

Returns converted value, units

exactFactorIndex (*key*)

Find the index of a factor that contains a key.

Parameters **key** – anything to look in factors (i.e. factor name, factor value, abbreviation).

Returns factor structure, else None.

factor

factors

getFactor (*key*)

Tries to find factor value in factors.

Parameters **key** – anything to look in factors (i.e. factor name, factor value, abbreviation). If key is a factor value it will look for the nearest factor value.

Returns factor structure, else raises error.

nearFactorIndex (*factor*)

Find the index of nearest factor value.

Parameters **factor** – factor value.

Returns factor structure near factor value.

static parts (*value, precision=4*)

Get number parts.

Parameters

- **value** – number

- **precision** – decimal precision

Returns ([... ,Hundreds, Tens, Ones],[Tenths, ...])

static split (*value*)

Get number fraction.

Parameters **value** – number

Returns integer, fraction

class `RRtoolbox.lib.root.Magnitude` (*value=0, factor=None, unit=None, precision=None, abbreviate=False*)

Bases: object

format_value (*value*)

class `RRtoolbox.lib.root.TimeCode` (*msg=None, factor=None, precision=None, abv=None, endmsg='{time}n', enableMsg=True, printfunc=None, profiler=None, profile_point=None*)

Bases: object

Context to profile code by printing a prelude and prologue with time.

Parameters

- **msg** – prelude or description message
- **factor** – factor supported by FactorConvert class
- **precision** – number of digits after a float point
- **abv** – if True prints “s”, if False “seconds” for time
- **endmsg** – prologue message
- **enableMsg** – (True) A flag specifying if context should be printed or not.
- **printfunc** – function to print messages. By default it is `sys.stdout.write`

time

time_end

`RRtoolbox.lib.root.addto` (*instance, funcname=None*)

Decorator: Add function as method to instance.

Parameters

- **instance** – class instance.
- **funcname** – name to register in instance.

Returns

`RRtoolbox.lib.root.decorateInstanceMethods` (*self, decorator, excludeMth='__init__', includeMth=None*)

Decorate methods in an instance. It should be used in the `__init__` method of a class.

Parameters

- **self** – class instance.
- **decorator** – decorator function to apply to self.
- **excludeMth** – list of methods to exclude.

- **includeMth** – list of methods to include if not in exclude. if excludeMth is None then decorateInstanceMethods checks for includeMth list. if includeMth and excludeMth is None then all methods of self are decorated.

Returns self

Note: It must be used at instance initialization (i.e. inside `__init__` method)

`RRtoolbox.lib.root.glob(path, contents='*', check=<function isfile>)`

Return a list of paths matching a pathname pattern with valid files.

Parameters

- **path** – path to process ing glob filter
- **contents** – If path is a folder then looks for contents using
- **check** – function to filter contents. it must receive the path and return True to let it pass and False to suppress it.

Returns return list of files

`RRtoolbox.lib.root.lookinglob(pattern, path, ext=None, returnAll=False, raiseErr=False)`

Parameters

- **pattern** – look pattern in path
- **path** – path to look pattern
- **ext** – extension
- **raiseErr** – If true raise Exception if patter not found in path

Returns fn or None

`class RRtoolbox.lib.root.profiler(msg=None, tag=None)`

Bases: object

profiler for code points

param msg custom comment for profiling point

param tag classification tag

parameter space (" ")

parameter format_line (" {space} {tag} {msg} {time} ")

parameter format_structure ("

{space} [{tag} {msg} {time} {child}] {side} ")

parameter points profile instaces which are divided in "side" or "children" points according if they are side by side or are inside of the profiler.

close()

close profiler and all their points

formatter(level, tag, msg, time)

format profiling point arguments.

Parameters

- **level** –

- **tag** – classification tag
- **msg** – custom comment of profiling point
- **time** – time of profiling

Returns formatted (spacing, tag, msg, time)

lines_formatted (*collapse=None*)
generate string lines

Parameters **collapse** – list for collapsing repeated tags or messages.

Returns list of lines

lines_unformatted (*collapse=None*)
generate structure lines

Parameters **collapse** – list for collapsing repeated tags or messages.

Returns generator with outputs (level, tag, msg, time)

open_point (*msg=None, tag=None*)
Open a profiling point to track time.

Parameters

- **msg** – custom comment for profiling point
- **tag** – classification tag

Returns

restructure (*structure, collapse*)
reprocess an already created structure.

Parameters

- **structure** – structure.
- **collapse** – list for collapsing repeated tags or messages.

Returns reprocessed structure

string_lines ()
string with plain structure of profiling

string_structured (*collapse=None, structure=None*)
string with plain structure of profiling

Parameters

- **collapse** – list for collapsing repeated tags or messages.
- **structure** – (None) uses and already created structure. If None it creates the structure.

Returns string

structure (*collapse=None*)
profiling structure.

Parameters **collapse** – list for collapsing repeated tags or messages.

Returns structure with format [tag,msg,time,children]

time

Returns overall time of profiling

class `RRtoolbox.lib.root.stdoutLOG` (*path, mode='w+', chain=False*)
 simple logger to save stdout output so anything printed in the console is logged to a file.

Parameters

- **path** – path to logging file
- **mode** – mode for opening the file.
- **chain** – if True closes previous logs and continues with new log

```
close (**kwargs)
flush (**kwargs)
printline (text, **kwargs)
printlines (lines, **kwargs)
write (text, **kwargs)
```

class `RRtoolbox.lib.root.stdoutMULTI` (*filelist*)
 Enclose several file-like objects.

:param *filelist* = list of file-like objects

```
close (**kwargs)
flush (**kwargs)
printline (text, **kwargs)
printlines (lines, **kwargs)
write (text, **kwargs)
```

class `RRtoolbox.lib.root.stdoutSIM` (*disable=False, stdout=None*)
 simple logger to simulate stdout output

```
close ()
flush ()
printline (text, **kwargs)
printlines (lines, **kwargs)
write (text, **kwargs)
```

RRtoolbox.lib.serverServices module

class `RRtoolbox.lib.serverServices.Connection` (*conn*)
 represent a connection to interchange objects between servers and clients.

```
getLen (timeout=None)
rcv ()
recvall ()
send (obj)
sendLen (length, timeout=None)
```

exception `RRtoolbox.lib.serverServices.TimeoutException`
 Bases: `exceptions.Exception`

exception `RRtoolbox.lib.serverServices.TransferException`

Bases: `exceptions.Exception`

`RRtoolbox.lib.serverServices.generateServer` (*host='localhost', to=63342*)

generates a simple Server in available address.

Parameters *to* – until port.

Returns socket, address

`RRtoolbox.lib.serverServices.initClient` (*addr, timeout=None*)

Init a simple client from address. :param *addr*: (host, port) :return: socket

`RRtoolbox.lib.serverServices.initServer` (*addr*)

Init a simple server from address.

Parameters *addr* – (host, port)

Returns socket

`RRtoolbox.lib.serverServices.parseString` (*string, timeout=3*)

Parameters

- *string* –
- *timeout* –

Returns

`RRtoolbox.lib.serverServices.ping` (*host, port*)

Ping to.

Parameters

- *host* – IP address
- *port* – port address

Returns

`RRtoolbox.lib.serverServices.rcvPickle` (*addr=('localhost', 50007), timeout=None*)

Receive potentially any data using sockets.

Parameters

- *addr* – socket or address.
- *timeout* – NotImplemented

Returns data, else throws error.

`RRtoolbox.lib.serverServices.recv_into` (*viewable, socket*)

Receive from socket into viewable object.

Parameters

- *viewable* – viewable object
- *socket* – source socket

Returns None

`RRtoolbox.lib.serverServices.scan_ports` (*host*)

Scan opened ports in address.

Parameters *host* – host IP to filter opened ports.

Returns generator

`RRtoolbox.lib.serverServices.sendPickle(obj, addr=('localhost', 50007), timeout=None, threaded=False)`

Send potentially any data using sockets.

Parameters

- **obj** – packable object.
- **addr** – socket or address.
- **timeout** – NotImplemented

Returns True if sent successfully, else Throw error.

`RRtoolbox.lib.serverServices.send_from(viewable, socket)`

Send from viewable object.

Parameters

- **viewable** – viewable object
- **socket** – destine socket

Returns None

`RRtoolbox.lib.serverServices.string_is_socket_address(string)`

RRtoolbox.lib.session module

This module have serializing methods for data persistence so to let the package “save” custom objects

session module made by Davtohi and powered by dill Dependency project: <https://github.com/uqfoundation/dill>

`RRtoolbox.lib.session.checkFromSession(filepath, varlist)`

Check that variables exists in session file.

Parameters

- **filepath** – path to session file.
- **varlist** – list of variables to checkLoaded.

Returns list checkLoaded results

`RRtoolbox.lib.session.deleteFromSession(filepath, varlist)`

Delete variables from session file.

Parameters

- **filepath** – path to session file.
- **varlist** – list of variables to delete.

Returns None

`RRtoolbox.lib.session.flushSession(filepath)`

Empty session in file.

Parameters **filepath** – path to session file.

Returns

`RRtoolbox.lib.session.getEnviromentSession(enviroment=None)`

Gets the filtered session from the global variables.

Returns dictionary containing filtered session.

`RRtoolbox.lib.session.readSession (filepath, helper=None)`

Loads a dictionary session from file.

Parameters

- **filepath** – path to load session file.
- **helper** – function to pos-process session file

Returns session

`RRtoolbox.lib.session.saveSession (filepath, session, helper=None)`

Saves dictionary session to file.

Parameters

- **filepath** – path to save session file.
- **session** – dictionary
- **helper** – function to pre-process session

Returns filename of saved session

`RRtoolbox.lib.session.updateSession (filepath, session, replace=True, rdhelper=None, svhelper=None)`

Updates a dictionary session in file.

Parameters

- **filepath** – path to session file.
- **session** – dictionary.
- **replace** – if True key values are replaced else old key values are kept.
- **rdhelper** – read helper.
- **svhelper** – save helper.

Returns None

Module contents

This module contains core-like, too-much-used and too-much-referenced modules

1.1.2 RRtoolbox.tools package

Submodules

RRtoolbox.tools.lens module

`RRtoolbox.tools.lens.drawCircle (array, cnt, color=0)`

project circle over array.

Parameters

- **array** – array to draw circle
- **cnt** – contours of segmentation to fit circle
- **color** – color of lens

Returns array

`RRtoolbox.tools.lens.drawEllipse(array, cnt, color=0)`
 project ellipse over array.

Parameters

- **array** – array to draw ellipse
- **cnt** – contours of segmentation to fit ellipse
- **color** – color of lens

Returns array

`RRtoolbox.tools.lens.fitLens(img, mask, color=0, asEllipse=False, addmask=False)`
 Place lens-like object in image.

Parameters

- **img** – image to place lens
- **mask** – mask to fit lens
- **color** – color of the lens
- **asEllipse** – True to fit lens as a ellipse, False to fit circle.
- **addmask** – return additional mask parameter

Returns image with simulated lens

`RRtoolbox.tools.lens.simulateLens(img, threshfunc=None, pshape=(300, 300), color=0, asEllipse=True)`
 Place lens-like object in image.

Parameters

- **img** – image to place lens.
- **threshfunc** – function to segment retinal area and get its mask.
- **pshape** – shape to resize processing image to increase performance.
- **color** – color of the lens.
- **asEllipse** – True to fit lens as a ellipse, False to fit circle.

Returns image with simulated lens.

RRtoolbox.tools.restoration module

`RRtoolbox.tools.restoration.asif_demo(fn_back=None, fn_fore=None, **opts)`
 Demo to test ASIFT, Merge, Plotters.

Parameters

- **fn_back** – file name of background image
- **fn_fore** – file name of foreground image
- ****opts** – demo options flag options: `flag_filter_scaled` (False): filter scaled images `flag_filter_original` (False): filter original images `flag_filter_out` (False): filter pos-processed images `flag_invertH` (False): test inversion of Trasformation Matrix obtained from Homography `flag_show_match` (True): show match keypoint of scaled images `flag_show_result` (True): show restored image `flag_save_perspective` (False): save calculated perspective of foreground image `flag_save_result` (False): save restored image

value options: `fore_scale` (400,400): tuple of W,H to convert original foreground to scaled image
`back_scale` (400,400): tuple of W,H to convert original background to scaled image
feature: ('sift-flann') use base descriptor

Returns

dictionary of results if there is not match the keys are:

['status', 'kp1', 'kp2', 'kp_pairs', 'desc1', 'desc2', 'H']

if there is match then additional keys are: ['img_perspective', 'img_restored', 'H_original', 'kp_pairs_original']

if `flag_invertH` additional keys: ['H_inverted']

`RRtoolbox.tools.restoration.asif_demo2` (*fn_back=None, fn_fore=None, **opts*)

Demo to test ASIFT, Merge, Plotters, etc while extending images.

Parameters

- **fn_back** – file name of background image
- **fn_fore** – file name of foreground image
- ****opts** – demo options flag options: `flag_filter_scaled` (False): filter scaled images
`flag_filter_original` (False): filter original images `flag_filter_out` (False): filter pos-processed images
`flag_invertH` (False): test inversion of Transformation Matrix obtained from Homography
`flag_show_match` (True): show match keypoint of scaled images `flag_show_result` (True): show restored image
`flag_save_perspective` (False): save calculated perspective of foreground image `flag_save_result` (False): save restored image

value options: `fore_scale` (400,400): tuple of W,H to convert original foreground to scaled image
`back_scale` (400,400): tuple of W,H to convert original background to scaled image
feature: ('sift-flann') use base descriptor

Returns

dictionary of results if there is not match the keys are:

['status', 'kp1', 'kp2', 'kp_pairs', 'desc1', 'desc2', 'H']

if there is match then additional keys are: ['img_perspective', 'img_restored', 'H_original', 'kp_pairs_original']

if `flag_invertH` additional keys: ['H_inverted']

`RRtoolbox.tools.restoration.extractCSV` (*data, saveTo=None*)

`RRtoolbox.tools.restoration.getDicDescriptor` (*path, loader, feature_name, dic=None*)

Parameters

- **path** –
- **loader** –
- **feature_name** –
- **dic** –

Returns

RRtoolbox.tools.restoration.**qualifyData** (*data*, *loader=None*, *saveTo=None*, *autoqualify=False*, *showOnlyPassedTest=False*, *clear=False*)

Qualify data of format obtained from testRates.

Parameters

- **data** – dictionary containing all data
- **loader** – use loader for images
- **saveTo** – save data to path
- **autoqualify** – qualify all data without asking human intervention and using algorithm
- **showOnlyPassedTest** – if True shows only the goods tests to qualify, else do not show.
- **clear** – re-do all saved tests.

Returns

RRtoolbox.tools.restoration.**stitch_multiple** (*images=None*, ***opts*)

Parameters *opts* –

feature = 'sift-flann' loader = "400,400" saveTo = None, autoqualify = False, showOnlyPassedTest= False, clearAll = False, clearData = clearAll, clearQualification = clearAll :return:

RRtoolbox.tools.restoration.**testRates** (*images=None*, ***opts*)

Parameters *opts* –

feature = 'sift-flann' loader = "400,400" saveTo = None, autoqualify = False, showOnlyPassedTest= False, clearAll = False, clearData = clearAll, clearQualification = clearAll :return:

RRtoolbox.tools.restoration.**watchData** (*request*, *loader*, *data*, *onlyTest=False*)

Show data of format obtained from testRates

Parameters

- **request** – (fore_name,back_name)
- **loader** – image loader from path
- **data** – dictionary containing requests (each request is a key).
- **onlyTest** – if True show only test results, else also show stitched images and some other data.

Returns request data.

RRtoolbox.tools.segmentation module

RRtoolbox.tools.segmentation.**find_optic_disc** (*img*, *P*)

find optic disk in image

Parameters

- **img** – BGR image
- **P** – gray image

Returns optic_disc, Crs, markers, watershed

RRtoolbox.tools.segmentation.**getBrightAlpha** (*backgray*, *foregray*, *window=None*)

Get alpha transparency for merging foreground to background gray image according to brightness.

Parameters

- **backgray** – background image. (as float)
- **foregray** – foreground image. (as float)
- **window** – window used to customizing alfa. It can be a binary or alfa mask, values go from 0 for transparency to any value where the maximum is visible i.e a window with all the same values does nothing. A binary mask can be used, where 0 is transparent and 1 is visible. If not window is given alfa is not altered and the intended alfa is returned.

Returns alfa mask

`RRtoolbox.tools.segmentation.get_beta_params(P)`
automatically find parameters for bright alpha masks.

Parameters **P** – gray image**Returns** beta1,beta2

`RRtoolbox.tools.segmentation.layeredfloods(img, gray=None, backmask=None, step=1, connectivity=4, weight=False)`

Parameters

- **img** –
- **gray** –
- **backmask** –
- **step** –
- **connectivity** –
- **weight** –

Returns

`RRtoolbox.tools.segmentation.retina_markers_thresh(P)`
Retinal markers thresholds to find background, retinal area and optic disc with flares based in the histogram

Parameters **P** – gray image**Returns** min,b1,b2,max

`RRtoolbox.tools.segmentation.retinal_mask(img, biggest=False, addalpha=False)`

Parameters

- **img** –
- **biggest** –
- **addalpha** –

Returns

`RRtoolbox.tools.segmentation.retinal_mask_simple(img, parameters=(10, 30, None))`

RRtoolbox.tools.selectors module

`RRtoolbox.tools.selectors.entropy(imlist, loadfunc=None, invert=False)`
Entropy function modified from:

Yan Liu, Feihong Yu, An automatic image fusion algorithm for unregistered multiply multi-focus images, Optics Communications, Volume 341, 15 April 2015,

Pages 101-113, ISSN 0030-4018, <http://dx.doi.org/10.1016/j.optcom.2014.12.015>.
(<http://www.sciencedirect.com/science/article/pii/S0030401814011559>)

Parameters `imlist` – list of path to images or arrays

Returns `sortedD,sortedImlist,D,fns`

where `sortedD` is the ranking of the Entropy test, `D = [D0,...,DN]` `D0>DN` `sortedImlist` is `fns` sorted to match `sortedD`, `D` is the list of the absolute difference between entropy and the root mean square, `D = |E-RMS|`

class `RRtoolbox.tools.selectors.entropyPlot` (`images`, `win='Entropy tests'`, `func=None`)

Bases: `RRtoolbox.lib.plotter.plotim`

Plot entropy test

getData (`im`)

getImage (`im`)

keyfunc ()

nextim ()

previousim ()

selectlist (`imlist`)

`RRtoolbox.tools.selectors.hist_comp` (`imlist`, `loadfunc=None`, `method='correlation'`)

Histogram comparison

Parameters `imlist` – list of path to images or arrays

Returns `comparison`

RRtoolbox.tools.sticher module

`RRtoolbox.tools.sticher.stich` (`**opts`)

Module contents

1.2 Submodules

1.3 RRtoolbox.core module

`RRtoolbox.core.f` (`*args`, `**kwargs`)

class `RRtoolbox.core.rrbox` (`*args`)

Bases: `object`

asift (`fn`)

`RRtoolbox.core.tools` (`instance`, `modules`)

`RRtoolbox.core.tools2` (`instance`, `modules`)

1.4 RRtoolbox.run module

1.5 RRtoolbox.shell module

exception `RRtoolbox.shell.NoParserFound`

Bases: `exceptions.Exception`

`RRtoolbox.shell.getDocParamLines (doc)`

gets each parameter line from reStructured doc.

Parameters `doc` – documentation

Returns lines

`RRtoolbox.shell.getDocParameters (doc)`

gets param and comment from reStructured doc.

Parameters `doc` – documentation

Returns list of (param,comment) items.

class `RRtoolbox.shell.shell`

generateParser (*func*)

getParser (*func*)

parse (*func*, *args=None*, *namespace=None*)

parser_fastplt ()

parser_loadFunc ()

`RRtoolbox.shell.shell_processor (commands)`

`RRtoolbox.shell.shell_processor_parser (syslist, flags='', longopts=('feature=', 'nnn='))`

1.6 Module contents

Indices and tables

- `genindex`
- `modindex`
- `search`

r

- RRtoolbox, 76
- RRtoolbox.core, 75
- RRtoolbox.lib, 70
 - arrayops, 26
 - basic, 3
 - convert, 18
 - filters, 21
 - mask, 24
 - cache, 26
 - config, 31
 - descriptors, 32
 - directory, 35
 - image, 40
 - inspector, 52
 - plotter, 54
 - root, 62
 - serverServices, 67
 - session, 69
- RRtoolbox.run, 76
- RRtoolbox.shell, 76
- RRtoolbox.tools, 75
 - lens, 70
 - restoration, 71
 - segmentation, 73
 - selectors, 74
 - sticher, 75

A

addto() (in module RRtoolbox.lib.root), 64
 affine_skew() (in module RRtoolbox.lib.descriptors), 34
 all (RRtoolbox.lib.cache.resourceManager attribute), 29
 alpha (RRtoolbox.lib.arrayops.filters.FilterBase attribute), 21
 angle() (in module RRtoolbox.lib.arrayops.basic), 3
 angle2D() (in module RRtoolbox.lib.arrayops.basic), 3
 angleXY() (in module RRtoolbox.lib.arrayops.basic), 4
 anorm() (in module RRtoolbox.lib.arrayops.basic), 4
 anorm2() (in module RRtoolbox.lib.arrayops.basic), 4
 apply2kp_pairs() (in module RRtoolbox.lib.arrayops.convert), 18
 applythresh() (RRtoolbox.lib.plotter.imtester static method), 56
 asif_demo() (in module RRtoolbox.tools.restoration), 71
 asif_demo2() (in module RRtoolbox.tools.restoration), 72
 ASIFT() (in module RRtoolbox.lib.descriptors), 32
 asift() (RRtoolbox.core.rrbox method), 75
 ASIFT_iter() (in module RRtoolbox.lib.descriptors), 33
 ASIFT_multiple() (in module RRtoolbox.lib.descriptors), 33
 Asynchronous (class in RRtoolbox.lib.inspector), 52
 axesIntercept() (in module RRtoolbox.lib.arrayops.basic), 4

B

background() (in module RRtoolbox.lib.arrayops.mask), 24
 background() (in module RRtoolbox.lib.plotter), 54
 bandpass (class in RRtoolbox.lib.arrayops.filters), 22
 bandstop (class in RRtoolbox.lib.arrayops.filters), 22
 beta1 (RRtoolbox.lib.arrayops.filters.FilterBase attribute), 21
 beta2 (RRtoolbox.lib.arrayops.filters.FilterBase attribute), 22
 bgra2bgr() (in module RRtoolbox.lib.image), 41
 biggestCnt() (in module RRtoolbox.lib.arrayops.mask), 24

biggestCntData() (in module RRtoolbox.lib.arrayops.mask), 24
 bilateralFilter() (in module RRtoolbox.lib.arrayops.filters), 22
 BilateralParameters (class in RRtoolbox.lib.arrayops.filters), 21
 bilateraP (class in RRtoolbox.lib.arrayops.filters), 22
 boxPads() (in module RRtoolbox.lib.arrayops.basic), 5
 brightness() (in module RRtoolbox.lib.arrayops.mask), 24
 broadcast() (RRtoolbox.lib.inspector.Logger method), 53
 builtincmd() (RRtoolbox.lib.plotter.imtester method), 56
 builtincmd() (RRtoolbox.lib.plotter.plotim method), 58
 builtincontrol() (RRtoolbox.lib.plotter.plotim method), 58
 builtinplot() (RRtoolbox.lib.plotter.plotim method), 58
 builtinwindow() (RRtoolbox.lib.plotter.plotim method), 58
 bytes2units() (RRtoolbox.lib.cache.resourceManager method), 29

C

cache (class in RRtoolbox.lib.cache), 27
 cachedir (RRtoolbox.lib.cache.DynamicMemoizedFunc attribute), 26
 cachedProperty() (in module RRtoolbox.lib.cache), 28
 call_and_shelve() (RRtoolbox.lib.cache.DynamicMemoizedFunc method), 26
 centerM() (in module RRtoolbox.lib.arrayops.basic), 5
 centerS() (in module RRtoolbox.lib.arrayops.basic), 5
 centerSM() (in module RRtoolbox.lib.arrayops.basic), 5
 changedir() (in module RRtoolbox.lib.directory), 35
 checkDir() (in module RRtoolbox.lib.directory), 36
 checkFile() (in module RRtoolbox.lib.directory), 36
 checkFromSession() (in module RRtoolbox.lib.session), 69
 checkLoaded() (in module RRtoolbox.lib.image), 41
 checkPath() (in module RRtoolbox.lib.directory), 36
 checkURL() (in module RRtoolbox.lib.directory), 36
 clean() (RRtoolbox.lib.plotter.plotim method), 58
 clear() (RRtoolbox.lib.cache.DynamicMemoizedFunc method), 26

clear() (RRtoolbox.lib.cache.memoizedDict method), 28
 close() (RRtoolbox.lib.root.profiler method), 65
 close() (RRtoolbox.lib.root.stdoutLOG method), 67
 close() (RRtoolbox.lib.root.stdoutMULTI method), 67
 close() (RRtoolbox.lib.root.stdoutSIM method), 67
 closefunc() (RRtoolbox.lib.plotter.plotim method), 58
 cmdfunc() (RRtoolbox.lib.plotter.plotim method), 58
 cnt2pts() (in module RRtoolbox.lib.arrayops.convert), 18
 cnt_hist() (in module RRtoolbox.lib.arrayops.mask), 24
 compress (RRtoolbox.lib.cache.DynamicMemoizedFunc attribute), 26
 computeAll() (RRtoolbox.lib.plotter.edger method), 55
 computeEdge() (RRtoolbox.lib.plotter.edger method), 55
 computefunc() (RRtoolbox.lib.plotter.imtester method), 56
 Conection (class in RRtoolbox.lib.serverServices), 67
 config() (RRtoolbox.lib.descriptors.Feature method), 33
 ConfigTool (class in RRtoolbox.lib.config), 31
 contour2points() (in module RRtoolbox.lib.arrayops.convert), 18
 contours2mask() (in module RRtoolbox.lib.arrayops.basic), 5
 contoursArea() (in module RRtoolbox.lib.arrayops.basic), 5
 Controlstdout (class in RRtoolbox.lib.root), 62
 conv3H4H() (in module RRtoolbox.lib.arrayops.convert), 18
 convert() (RRtoolbox.lib.root.FactorConvert method), 63
 convert2bgr() (in module RRtoolbox.lib.plotter), 54
 convert2bgra() (in module RRtoolbox.lib.plotter), 54
 convert2sample() (RRtoolbox.lib.root.FactorConvert method), 63
 convertAs() (in module RRtoolbox.lib.image), 41
 convertXY() (in module RRtoolbox.lib.arrayops.basic), 5
 convexityRatio() (in module RRtoolbox.lib.arrayops.basic), 6
 coors (RRtoolbox.lib.image.getCoors attribute), 43
 copy() (RRtoolbox.lib.directory.directory method), 37
 correctPath() (in module RRtoolbox.lib.directory), 36
 correctSep() (in module RRtoolbox.lib.directory), 36
 correctSTRBuiltin() (RRtoolbox.lib.directory.directory method), 37
 create() (RRtoolbox.lib.cache.objectGetter method), 29

D

d (RRtoolbox.lib.arrayops.filters.BilateralParameters attribute), 21
 decorateInstanceMethods() (in module RRtoolbox.lib.root), 64
 decoratePath() (in module RRtoolbox.lib.directory), 36
 default (RRtoolbox.lib.config.directoryManager attribute), 31
 deleteFromSession() (in module RRtoolbox.lib.session), 69

detectAndCompute() (RRtoolbox.lib.descriptors.Feature method), 33
 detectType() (RRtoolbox.lib.plotter.imtester method), 56
 dict2keyPoint() (in module RRtoolbox.lib.arrayops.convert), 18
 directory (class in RRtoolbox.lib.directory), 36
 directoryManager (class in RRtoolbox.lib.config), 31
 done() (RRtoolbox.lib.inspector.Asynchronous method), 52
 done() (RRtoolbox.lib.inspector.graphTraceOutput method), 53
 drawCircle() (in module RRtoolbox.tools.lens), 70
 drawcoorarea() (in module RRtoolbox.lib.image), 41
 drawcooraxes() (in module RRtoolbox.lib.image), 42
 drawcoorperspective() (in module RRtoolbox.lib.image), 42
 drawcoorpoints() (in module RRtoolbox.lib.image), 42
 drawcoorpolyArrow() (in module RRtoolbox.lib.image), 42
 drawcoorpolyline() (in module RRtoolbox.lib.image), 43
 drawEllipse() (in module RRtoolbox.tools.lens), 70
 drawline() (RRtoolbox.lib.plotter.matchExplorer method), 57
 drawrelation() (RRtoolbox.lib.plotter.matchExplorer method), 57
 drawstats() (RRtoolbox.lib.image.getCoors method), 44
 dtype (RRtoolbox.lib.image.imcoors attribute), 47
 DynamicMemoizedFunc (class in RRtoolbox.lib.cache), 26

E

echo() (in module RRtoolbox.lib.plotter), 54
 edger (class in RRtoolbox.lib.plotter), 54
 enabled (RRtoolbox.lib.cache.DynamicMemoizedFunc attribute), 26
 entropy() (in module RRtoolbox.tools.selectors), 74
 entropyPlot (class in RRtoolbox.tools.selectors), 75
 entroyTest() (in module RRtoolbox.lib.arrayops.basic), 6
 errorbackground (RRtoolbox.lib.plotter.plotim attribute), 59
 eventHandle (RRtoolbox.lib.inspector.Logger attribute), 53
 exactFactorIndex() (RRtoolbox.lib.root.FactorConvert method), 63
 extractCSV() (in module RRtoolbox.tools.restoration), 72

F

f() (in module RRtoolbox.core), 75
 factor (RRtoolbox.lib.root.FactorConvert attribute), 63
 FactorConvert (class in RRtoolbox.lib.root), 63
 factors (RRtoolbox.lib.root.FactorConvert attribute), 63
 fastplt() (in module RRtoolbox.lib.plotter), 55
 Feature (class in RRtoolbox.lib.descriptors), 33
 fig2bgr() (in module RRtoolbox.lib.image), 43

fig2bgra() (in module RRtoolbox.lib.image), 43
 file (RRtoolbox.lib.inspector.Logger attribute), 53
 FileDirectory (class in RRtoolbox.lib.directory), 35
 filter_matches() (in module RRtoolbox.lib.descriptors), 34
 FilterBase (class in RRtoolbox.lib.arrayops.filters), 21
 filterdata() (RRtoolbox.lib.directory.directory static method), 37
 filterFactory() (in module RRtoolbox.lib.arrayops.filters), 22
 filters (RRtoolbox.lib.arrayops.filters.BilateralParameters attribute), 21
 find_near() (in module RRtoolbox.lib.arrayops.basic), 6
 find_optic_disc() (in module RRtoolbox.tools.segmentation), 73
 findmaxima() (in module RRtoolbox.lib.arrayops.basic), 6
 findminima() (in module RRtoolbox.lib.arrayops.basic), 7
 findModules() (in module RRtoolbox.lib.config), 32
 fitLens() (in module RRtoolbox.tools.lens), 71
 flush() (RRtoolbox.lib.root.stdoutLOG method), 67
 flush() (RRtoolbox.lib.root.stdoutMULTI method), 67
 flush() (RRtoolbox.lib.root.stdoutSIM method), 67
 flushSession() (in module RRtoolbox.lib.session), 69
 foreground() (in module RRtoolbox.lib.arrayops.mask), 25
 format_value() (RRtoolbox.lib.root.Magnitude method), 64
 formatcmd() (RRtoolbox.lib.plotter.plotim method), 59
 formatinfo() (RRtoolbox.lib.plotter.imtester static method), 56
 formatter() (RRtoolbox.lib.root.profiler method), 65
 func (RRtoolbox.lib.cache.DynamicMemoizedFunc attribute), 26
 funcData() (in module RRtoolbox.lib.inspector), 53

G

generateParser() (RRtoolbox.shell.shell method), 76
 generateServer() (in module RRtoolbox.lib.serverServices), 68
 get_beta_params() (in module RRtoolbox.tools.segmentation), 74
 get_code() (RRtoolbox.lib.image.imFactory method), 45
 get_conversionFunc() (RRtoolbox.lib.image.imFactory method), 45
 get_errorFunc() (RRtoolbox.lib.image.imFactory method), 45
 get_Func() (RRtoolbox.lib.image.imFactory method), 45
 get_loadFunc() (RRtoolbox.lib.image.imFactory method), 45
 get_mapFunc() (RRtoolbox.lib.image.imFactory method), 45
 get_np2qi() (RRtoolbox.lib.image.imFactory method), 45

get_resizeFunc() (RRtoolbox.lib.image.imFactory method), 45
 get_tracer_class() (RRtoolbox.lib.inspector.graphTrace method), 53
 get_transposeFunc() (RRtoolbox.lib.image.imFactory method), 45
 get_x_space() (in module RRtoolbox.lib.arrayops.basic), 7
 getBilateralParameters() (in module RRtoolbox.lib.arrayops.filters), 22
 getBrightAlpha() (in module RRtoolbox.tools.segmentation), 73
 getConfiguration() (RRtoolbox.lib.image.imLoader method), 46
 getCoors (class in RRtoolbox.lib.image), 43
 getcoors() (in module RRtoolbox.lib.image), 44
 getData() (in module RRtoolbox.lib.directory), 38
 getData() (RRtoolbox.tools.selectors.entropyPlot method), 75
 getdataVH() (in module RRtoolbox.lib.arrayops.basic), 7
 getDicDescriptor() (in module RRtoolbox.tools.restoration), 72
 getDocParameters() (in module RRtoolbox.shell), 76
 getDocParamLines() (in module RRtoolbox.shell), 76
 getEnviromentSession() (in module RRtoolbox.lib.session), 69
 getFactor() (RRtoolbox.lib.root.FactorConvert method), 63
 getFileHandle() (in module RRtoolbox.lib.directory), 38
 getFileSize() (in module RRtoolbox.lib.directory), 38
 getgeometrycoors() (in module RRtoolbox.lib.image), 44
 gethull() (in module RRtoolbox.lib.arrayops.mask), 25
 getImage() (RRtoolbox.tools.selectors.entropyPlot method), 75
 getLen() (RRtoolbox.lib.serverServices.Connection method), 67
 getModules() (in module RRtoolbox.lib.config), 32
 getObj() (RRtoolbox.lib.cache.objectGetter method), 29
 getOtsuThresh() (in module RRtoolbox.lib.arrayops.basic), 7
 getPackagePath() (in module RRtoolbox.lib.config), 32
 getParameters() (RRtoolbox.lib.plotter.edger method), 55
 getParser() (RRtoolbox.shell.shell method), 76
 getPath() (in module RRtoolbox.lib.directory), 38
 getrectcoors() (in module RRtoolbox.lib.image), 44
 getSep() (in module RRtoolbox.lib.directory), 38
 getShortenedPath() (in module RRtoolbox.lib.directory), 38
 getSizeOf() (RRtoolbox.lib.cache.resourceManager method), 29
 getSOpointRelation() (in module RRtoolbox.lib.arrayops.convert), 18
 getSplitted() (in module RRtoolbox.lib.directory), 39
 getTools() (RRtoolbox.lib.config.ConfigTool static

method), 31
getTransformedCorners() (in module RRtoolbox.lib.arrayops.basic), 7
getTransparency() (in module RRtoolbox.lib.arrayops.basic), 7
glob() (in module RRtoolbox.lib.root), 65
graph_filter() (in module RRtoolbox.lib.plotter), 55
graphTrace (class in RRtoolbox.lib.inspector), 53
graphTraceOutput (class in RRtoolbox.lib.inspector), 53
gray2qi() (in module RRtoolbox.lib.image), 44

H

help() (RRtoolbox.lib.plotter.plotim method), 59
highpass (class in RRtoolbox.lib.arrayops.filters), 23
hist_cdf() (in module RRtoolbox.lib.arrayops.mask), 25
hist_comp() (in module RRtoolbox.tools.selectors), 75
hist_match() (in module RRtoolbox.lib.image), 44
histogram() (in module RRtoolbox.lib.arrayops.basic), 8

I

ignore (RRtoolbox.lib.cache.DynamicMemoizedFunc attribute), 26
ignore (RRtoolbox.lib.cache.Memoizer attribute), 27
im2imFormat() (in module RRtoolbox.lib.arrayops.basic), 8
im2shapeFormat() (in module RRtoolbox.lib.arrayops.basic), 8
imcoors (class in RRtoolbox.lib.image), 47
imFactory (class in RRtoolbox.lib.image), 44
imLoader (class in RRtoolbox.lib.image), 45
imtester (class in RRtoolbox.lib.plotter), 56
increment_if_exists() (in module RRtoolbox.lib.directory), 39
init() (RRtoolbox.lib.plotter.plotim method), 59
init_feature() (in module RRtoolbox.lib.descriptors), 34
initClient() (in module RRtoolbox.lib.serverServices), 68
initServer() (in module RRtoolbox.lib.serverServices), 68
inlineRatio() (in module RRtoolbox.lib.descriptors), 35
insert() (RRtoolbox.lib.image.pathLoader method), 51
instability_bf() (in module RRtoolbox.lib.arrayops.basic), 8
interpretImage() (in module RRtoolbox.lib.image), 47
invertedbandpass (class in RRtoolbox.lib.arrayops.filters), 23
invertedbandstop (class in RRtoolbox.lib.arrayops.filters), 23
invertH() (in module RRtoolbox.lib.arrayops.convert), 19
invertM() (in module RRtoolbox.lib.arrayops.basic), 8
invertSM() (in module RRtoolbox.lib.arrayops.basic), 8
isActiveWindow() (RRtoolbox.lib.plotter.edger method), 55
isAlive() (RRtoolbox.lib.cache.objectGetter method), 29
isBFILTER (RRtoolbox.lib.plotter.edger attribute), 55
isCLAHE (RRtoolbox.lib.plotter.edger attribute), 55

isCreatable() (RRtoolbox.lib.cache.objectGetter method), 29
isEQUA (RRtoolbox.lib.plotter.edger attribute), 55
isGettable() (RRtoolbox.lib.cache.objectGetter method), 29
isnumpy() (in module RRtoolbox.lib.arrayops.basic), 9
isSIZE (RRtoolbox.lib.plotter.edger attribute), 55

J

joinPath() (in module RRtoolbox.lib.directory), 39

K

keepAlive() (RRtoolbox.lib.cache.resourceManager method), 29
keyfunc() (RRtoolbox.lib.plotter.matchExplorer method), 57
keyfunc() (RRtoolbox.lib.plotter.plotim method), 59
keyfunc() (RRtoolbox.tools.selectors.entropyPlot method), 75
keyPoint2tuple() (in module RRtoolbox.lib.arrayops.convert), 19

L

layeredfloods() (in module RRtoolbox.tools.segmentation), 74
limitaxis() (in module RRtoolbox.lib.plotter), 56
limitaxispoints() (in module RRtoolbox.lib.image), 47
lines_formatted() (RRtoolbox.lib.root.profiler method), 66
lines_unformatted() (RRtoolbox.lib.root.profiler method), 66
load() (in module RRtoolbox.lib.inspector), 53
load() (RRtoolbox.lib.config.directoryManager method), 32
load() (RRtoolbox.lib.plotter.edger method), 55
loadcv() (in module RRtoolbox.lib.image), 49
loaderDict (class in RRtoolbox.lib.image), 50
loadFunc() (in module RRtoolbox.lib.image), 47
loadsfrom() (in module RRtoolbox.lib.image), 50
Logger (class in RRtoolbox.lib.inspector), 52
lookinglob() (in module RRtoolbox.lib.root), 65
lowpass (class in RRtoolbox.lib.arrayops.filters), 23

M

Magnitude (class in RRtoolbox.lib.root), 64
makeFile() (RRtoolbox.lib.directory.FileDirectory method), 35
makememory() (RRtoolbox.lib.cache.Memoizer method), 27
makeoverlay() (RRtoolbox.lib.plotter.plotim method), 59
makeVis() (in module RRtoolbox.lib.arrayops.basic), 9
mapper() (in module RRtoolbox.lib.cache), 28
margin (RRtoolbox.lib.cache.resourceManager attribute), 29

- mask_watershed() (in module RRtoolbox.lib.arrayops.mask), 25
- MATCH() (in module RRtoolbox.lib.descriptors), 34
- MATCH_multiple() (in module RRtoolbox.lib.descriptors), 34
- matchExplorer (class in RRtoolbox.lib.plotter), 56
- matrixIntercept() (in module RRtoolbox.lib.arrayops.basic), 9
- maxMemory (RRtoolbox.lib.cache.resourceManager attribute), 30
- maxth (RRtoolbox.lib.plotter.edger attribute), 55
- memoize() (RRtoolbox.lib.cache.Memoizer method), 27
- memoizedDict (class in RRtoolbox.lib.cache), 28
- Memoizer (class in RRtoolbox.lib.cache), 27
- memoizers (RRtoolbox.lib.cache.Memoizer attribute), 27
- MemorizedFunc (class in RRtoolbox.lib.cache), 27
- Memory (class in RRtoolbox.lib.cache), 27
- mkPath() (in module RRtoolbox.lib.directory), 39
- mmap_mode (RRtoolbox.lib.cache.DynamicMemoizedFunc attribute), 27
- mousefunc() (RRtoolbox.lib.image.getCoors method), 44
- mousefunc() (RRtoolbox.lib.plotter.matchExplorer method), 57
- mousefunc() (RRtoolbox.lib.plotter.plotim method), 59
- multiple_otsu() (in module RRtoolbox.lib.arrayops.mask), 25
- multiple_superpose() (in module RRtoolbox.lib.arrayops.basic), 9
- myline() (in module RRtoolbox.lib.image), 50
- ## N
- nearFactorIndex() (RRtoolbox.lib.root.FactorConvert method), 63
- nextim() (RRtoolbox.tools.selectors.entropyPlot method), 75
- noisy() (in module RRtoolbox.lib.arrayops.basic), 9
- NoParserFound, 76
- normalize() (in module RRtoolbox.lib.arrayops.basic), 10
- normalize2() (in module RRtoolbox.lib.arrayops.basic), 10
- normalizeCustom() (in module RRtoolbox.lib.arrayops.basic), 10
- normsigmoid() (in module RRtoolbox.lib.arrayops.filters), 23
- notCallable, 28
- notCreatable, 28
- NotMemorizedFunc (class in RRtoolbox.lib.cache), 27
- np2qi() (in module RRtoolbox.lib.image), 50
- np2str() (in module RRtoolbox.lib.image), 51
- ## O
- objectGetter (class in RRtoolbox.lib.cache), 28
- onmouse() (RRtoolbox.lib.plotter.plotim static method), 59
- onTrackbar1() (RRtoolbox.lib.plotter.edger method), 55
- onTrackbar2() (RRtoolbox.lib.plotter.edger method), 55
- open_point() (RRtoolbox.lib.root.profiler method), 66
- optimizeObject() (RRtoolbox.lib.cache.resourceManager method), 30
- overlay() (in module RRtoolbox.lib.arrayops.basic), 10
- overlay2() (in module RRtoolbox.lib.arrayops.basic), 10
- overlaypng() (in module RRtoolbox.lib.arrayops.basic), 12
- overlayXY() (in module RRtoolbox.lib.arrayops.basic), 11
- ## P
- pad_to_fit_H() (in module RRtoolbox.lib.arrayops.basic), 12
- padVH() (in module RRtoolbox.lib.arrayops.basic), 12
- parse() (RRtoolbox.shell.shell method), 76
- parser_fastplt() (RRtoolbox.shell.shell method), 76
- parser_loadFunc() (RRtoolbox.shell.shell method), 76
- parseString() (in module RRtoolbox.lib.serverServices), 68
- parts() (RRtoolbox.lib.root.FactorConvert static method), 63
- pathLoader (class in RRtoolbox.lib.image), 51
- ping() (in module RRtoolbox.lib.serverServices), 68
- plotatpointer() (RRtoolbox.lib.plotter.plotim method), 60
- plotatxy() (RRtoolbox.lib.plotter.plotim method), 60
- plotim (class in RRtoolbox.lib.plotter), 57
- plotintime() (RRtoolbox.lib.plotter.plotim method), 61
- plotPointsContour() (in module RRtoolbox.lib.plotter), 57
- plt2bgr() (in module RRtoolbox.lib.image), 51
- plt2bgra() (in module RRtoolbox.lib.image), 51
- points2contour() (in module RRtoolbox.lib.arrayops.convert), 19
- points2mask() (in module RRtoolbox.lib.arrayops.basic), 13
- points2vectos() (in module RRtoolbox.lib.arrayops.convert), 19
- points_generator() (in module RRtoolbox.lib.arrayops.basic), 13
- polygonArea() (in module RRtoolbox.lib.arrayops.basic), 13
- polygonArea_calcule() (in module RRtoolbox.lib.arrayops.basic), 13
- polygonArea_contour() (in module RRtoolbox.lib.arrayops.basic), 14
- polygonArea_fill() (in module RRtoolbox.lib.arrayops.basic), 14
- previousim() (RRtoolbox.tools.selectors.entropyPlot method), 75
- println() (RRtoolbox.lib.root.stdoutLOG method), 67
- println() (RRtoolbox.lib.root.stdoutMULTI method), 67
- println() (RRtoolbox.lib.root.stdoutSIM method), 67
- printlns() (RRtoolbox.lib.root.stdoutLOG method), 67

printlns() (RRtoolbox.lib.root.stdoutMULTI method), 67
printlns() (RRtoolbox.lib.root.stdoutSIM method), 67
process_as_blocks() (in module RRtoolbox.lib.arrayops.basic), 14
profiler (class in RRtoolbox.lib.root), 65
pts (RRtoolbox.lib.image.imcoors attribute), 47
pts2cnt() (in module RRtoolbox.lib.arrayops.convert), 19

Q

qi2np() (in module RRtoolbox.lib.image), 51
quadrant() (in module RRtoolbox.lib.arrayops.basic), 14
quadrants() (in module RRtoolbox.lib.image), 51
qualifyData() (in module RRtoolbox.tools.restoration), 72
quickOps() (in module RRtoolbox.lib.directory), 39

R

random_points() (in module RRtoolbox.lib.arrayops.basic), 14
randomColor() (RRtoolbox.lib.plotter.matchExplorer static method), 57
raw() (RRtoolbox.lib.cache.objectGetter method), 29
rcv() (RRtoolbox.lib.serverServices.Conection method), 67
rcvPickle() (in module RRtoolbox.lib.serverServices), 68
readSession() (in module RRtoolbox.lib.session), 69
real2render() (RRtoolbox.lib.plotter.plotim method), 61
recursiveMap() (in module RRtoolbox.lib.arrayops.basic), 15
recv_into() (in module RRtoolbox.lib.serverServices), 68
recvall() (RRtoolbox.lib.serverServices.Conection method), 67
register() (RRtoolbox.lib.cache.resourceManager method), 30
register() (RRtoolbox.lib.cache.retriever method), 30
register() (RRtoolbox.lib.image.loaderDict method), 50
relativeQuadrants() (in module RRtoolbox.lib.arrayops.basic), 15
relativeVectors() (in module RRtoolbox.lib.arrayops.basic), 15
reloadFunc() (in module RRtoolbox.lib.inspector), 53
render2real() (RRtoolbox.lib.plotter.plotim method), 61
renew() (RRtoolbox.lib.inspector.Logger method), 53
report() (RRtoolbox.lib.inspector.Logger method), 53
repr2list() (RRtoolbox.lib.directory.directory static method), 37
repr2str() (RRtoolbox.lib.directory.directory static method), 37
rescale() (in module RRtoolbox.lib.arrayops.basic), 15
reset() (RRtoolbox.lib.config.directoryManager method), 32
resetGetter() (RRtoolbox.lib.cache.resourceManager static method), 30
resource_path() (in module RRtoolbox.lib.directory), 40

resourceManager (class in RRtoolbox.lib.cache), 29
restructure() (RRtoolbox.lib.root.profiler method), 66
retina_markers_thresh() (in module RRtoolbox.tools.segmentation), 74
retinal_mask() (in module RRtoolbox.tools.segmentation), 74
retinal_mask_simple() (in module RRtoolbox.tools.segmentation), 74
retriever (class in RRtoolbox.lib.cache), 30
rgb2qi() (in module RRtoolbox.lib.image), 51
rmFile() (in module RRtoolbox.lib.directory), 40
rmPath() (in module RRtoolbox.lib.directory), 40
rrbox (class in RRtoolbox.core), 75
RRtoolbox (module), 76
RRtoolbox.core (module), 75
RRtoolbox.lib (module), 70
RRtoolbox.lib.arrayops (module), 26
RRtoolbox.lib.arrayops.basic (module), 3
RRtoolbox.lib.arrayops.convert (module), 18
RRtoolbox.lib.arrayops.filters (module), 21
RRtoolbox.lib.arrayops.mask (module), 24
RRtoolbox.lib.cache (module), 26
RRtoolbox.lib.config (module), 31
RRtoolbox.lib.descriptors (module), 32
RRtoolbox.lib.directory (module), 35
RRtoolbox.lib.image (module), 40
RRtoolbox.lib.inspector (module), 52
RRtoolbox.lib.plotter (module), 54
RRtoolbox.lib.root (module), 62
RRtoolbox.lib.serverServices (module), 67
RRtoolbox.lib.session (module), 69
RRtoolbox.run (module), 76
RRtoolbox.shell (module), 76
RRtoolbox.tools (module), 75
RRtoolbox.tools.lens (module), 70
RRtoolbox.tools.restoration (module), 71
RRtoolbox.tools.segmentation (module), 73
RRtoolbox.tools.selectors (module), 74
RRtoolbox.tools.sticher (module), 75
rx1 (RRtoolbox.lib.plotter.plotim attribute), 61
rx2 (RRtoolbox.lib.plotter.plotim attribute), 61
ry1 (RRtoolbox.lib.plotter.plotim attribute), 61
ry2 (RRtoolbox.lib.plotter.plotim attribute), 61

S

save() (RRtoolbox.lib.config.directoryManager method), 32
save() (RRtoolbox.lib.inspector.graphTraceOutput method), 53
save() (RRtoolbox.lib.plotter.edger method), 55
save() (RRtoolbox.lib.plotter.plotim method), 61
saveSession() (in module RRtoolbox.lib.session), 70
saveSource() (RRtoolbox.lib.inspector.graphTrace method), 53

- saveSource() (RRtoolbox.lib.inspector.graphTraceOutput method), 53
 scan_ports() (in module RRtoolbox.lib.serverServices), 68
 selectlist() (RRtoolbox.tools.selectors.entropyPlot method), 75
 send() (RRtoolbox.lib.serverServices.Connection method), 67
 send_from() (in module RRtoolbox.lib.serverServices), 69
 sendLen() (RRtoolbox.lib.serverServices.Connection method), 67
 sendPickle() (in module RRtoolbox.lib.serverServices), 68
 separe() (in module RRtoolbox.lib.image), 51
 separePointsByAxis() (in module RRtoolbox.lib.arrayops.basic), 15
 sh2oh() (in module RRtoolbox.lib.arrayops.convert), 19
 shell (class in RRtoolbox.shell), 76
 shell_processor() (in module RRtoolbox.shell), 76
 shell_processor_parser() (in module RRtoolbox.shell), 76
 show() (RRtoolbox.lib.plotter.plotim method), 62
 showfunc() (RRtoolbox.lib.plotter.plotim method), 62
 showgray (RRtoolbox.lib.plotter.edger attribute), 55
 sigmaColor (RRtoolbox.lib.arrayops.filters.BilateralParameters attribute), 21
 sigmaSpace (RRtoolbox.lib.arrayops.filters.BilateralParameters attribute), 21
 sigmoid() (in module RRtoolbox.lib.arrayops.filters), 23
 SimKeyPoint (class in RRtoolbox.lib.arrayops.convert), 18
 simulateLens() (in module RRtoolbox.tools.lens), 71
 size (RRtoolbox.lib.plotter.edger attribute), 55
 smooth() (in module RRtoolbox.lib.arrayops.filters), 23
 source (RRtoolbox.lib.inspector.graphTrace attribute), 53
 spairs2opairs() (in module RRtoolbox.lib.arrayops.convert), 20
 split() (RRtoolbox.lib.root.FactorConvert static method), 64
 splitPoints() (in module RRtoolbox.lib.arrayops.basic), 15
 spoint2opointfunc() (in module RRtoolbox.lib.arrayops.convert), 20
 standarizePoints() (in module RRtoolbox.lib.arrayops.basic), 16
 start() (RRtoolbox.lib.inspector.Asynchronous method), 52
 start() (RRtoolbox.lib.inspector.Synchronous method), 53
 stdoutLOG (class in RRtoolbox.lib.root), 66
 stdoutMULTI (class in RRtoolbox.lib.root), 67
 stdoutSIM (class in RRtoolbox.lib.root), 67
 stich() (in module RRtoolbox.tools.sticher), 75
 stitch_multiple() (in module RRtoolbox.tools.restoration), 73
 stop() (RRtoolbox.lib.inspector.Synchronous method), 53
 str2np() (in module RRtoolbox.lib.image), 52
 strdifference() (in module RRtoolbox.lib.directory), 40
 string_is_socket_address() (in module RRtoolbox.lib.serverServices), 69
 string_lines() (RRtoolbox.lib.root.profiler method), 66
 string_structured() (RRtoolbox.lib.root.profiler method), 66
 structure() (RRtoolbox.lib.root.profiler method), 66
 superpose() (in module RRtoolbox.lib.arrayops.basic), 16
 Synchronous (class in RRtoolbox.lib.inspector), 53
- ## T
- temp() (RRtoolbox.lib.image.imLoader method), 46
 testRates() (in module RRtoolbox.tools.restoration), 73
 textbackground (RRtoolbox.lib.plotter.plotim attribute), 62
 th1 (RRtoolbox.lib.plotter.edger attribute), 55
 th2 (RRtoolbox.lib.plotter.edger attribute), 55
 thresh_biggestCnt() (in module RRtoolbox.lib.arrayops.mask), 25
 thresh_hist() (in module RRtoolbox.lib.arrayops.mask), 25
 threshold_opening() (in module RRtoolbox.lib.arrayops.mask), 26
 throwError() (RRtoolbox.lib.inspector.Logger method), 53
 time (RRtoolbox.lib.root.profiler attribute), 66
 time (RRtoolbox.lib.root.TimeCode attribute), 64
 Time_ (RRtoolbox.lib.inspector.Logger attribute), 53
 time_end (RRtoolbox.lib.root.TimeCode attribute), 64
 TimeCode (class in RRtoolbox.lib.root), 64
 TimeoutException, 67
 tools() (in module RRtoolbox.core), 75
 tools2() (in module RRtoolbox.core), 75
 toTuple() (in module RRtoolbox.lib.arrayops.convert), 20
 tracer (RRtoolbox.lib.inspector.Logger attribute), 53
 tracer() (in module RRtoolbox.lib.inspector), 53
 tracer() (RRtoolbox.lib.inspector.Asynchronous method), 52
 TransferExeption, 67
 transformPoint() (in module RRtoolbox.lib.arrayops.basic), 16
 transformPoints() (in module RRtoolbox.lib.arrayops.basic), 16
 translateQuadrants() (in module RRtoolbox.lib.arrayops.convert), 20
 transposeIm() (in module RRtoolbox.lib.image), 52
 try_loads() (in module RRtoolbox.lib.image), 52
 tuple2keyPoint() (in module RRtoolbox.lib.arrayops.convert), 21
 Type_ (RRtoolbox.lib.inspector.Logger attribute), 53

U

unit (RRtoolbox.lib.cache.resourceManager attribute), 30
unit_vector() (in module RRtoolbox.lib.arrayops.basic), 16
units2bytes() (RRtoolbox.lib.cache.resourceManager method), 30
update() (RRtoolbox.lib.cache.objectGetter method), 29
update() (RRtoolbox.lib.directory.directory method), 37
update() (RRtoolbox.lib.image.imFactory method), 45
update_left() (RRtoolbox.lib.directory.directory method), 37
update_right() (RRtoolbox.lib.directory.directory method), 37
updatecoors() (RRtoolbox.lib.image.getCoors method), 44
updaterenderer() (RRtoolbox.lib.plotter.matchExplorer method), 57
updaterenderer() (RRtoolbox.lib.plotter.plotim method), 62
updateSession() (in module RRtoolbox.lib.session), 70
updatevisualization() (RRtoolbox.lib.plotter.imtester method), 56
usedMemory (RRtoolbox.lib.cache.resourceManager attribute), 30

V

vectorsAngles() (in module RRtoolbox.lib.arrayops.basic), 16
vectorsQuadrants() (in module RRtoolbox.lib.arrayops.basic), 17
vectos2points() (in module RRtoolbox.lib.arrayops.convert), 21
verbose (RRtoolbox.lib.cache.DynamicMemoizedFunc attribute), 27
vertexesAngles() (in module RRtoolbox.lib.arrayops.basic), 17
view_as_blocks() (in module RRtoolbox.lib.arrayops.basic), 17
view_as_windows() (in module RRtoolbox.lib.arrayops.basic), 17
visualize() (RRtoolbox.lib.plotter.imtester method), 56

W

watchData() (in module RRtoolbox.tools.restoration), 73
windowfunc() (RRtoolbox.lib.plotter.edger method), 55
windowfunc() (RRtoolbox.lib.plotter.imtester method), 56
windowfunc() (RRtoolbox.lib.plotter.plotim method), 62
write() (RRtoolbox.lib.root.stdoutLOG method), 67
write() (RRtoolbox.lib.root.stdoutMULTI method), 67
write() (RRtoolbox.lib.root.stdoutSIM method), 67
writer() (RRtoolbox.lib.inspector.Logger method), 53